

Honeywell

SERIES 600/6000

SOFTWARE

**INTEGRATED DATA STORE
REFERENCE MANUAL**

Honeywell

SERIES 600/6000

INTEGRATED DATA STORE REFERENCE MANUAL

SUBJECT:

General Description, Data Organization, Source Language, Programming Information, Operational Characteristics, and Capabilities of the Integrated Data Store (I-D-S) System.

SPECIAL INSTRUCTIONS:

This manual, order number BR69, Rev. 0, is a reprint of CPB-1565B, dated January 15, 1971. The new order number is assigned to be consistent with the overall Honeywell publications numbering system. The contents of this reprinted manual are the same as for CPB-1565B. Both CPB-1565B and BR69, Rev. 0, completely supersede the previous edition (CPB-1565A) and incorporate the information published in TIB 1565A-1, 1565A-2, and 1565A-3. New features implemented in *Series 600 System Development Letter 3.3* are also included. New information and changes since the last edition are indicated by change bars; deletions are indicated by asterisks.

INCLUDES UPDATING PAGES PUBLISHED AS ADDENDUM A IN AUGUST, 1971, WHICH INCLUDE NEW FEATURES IMPLEMENTED IN SERIES 600 SYSTEM DEVELOPMENT LETTER 4.0 AND SERIES 6000 SYSTEM DEVELOPMENT LETTER B.

DATE:

January, 1971

ORDER NUMBER: BR69 (Formerly CPB-1565)

Rev. 0

Preface

This manual describes the Integrated Data Store (I-D-S) system, which is an information-oriented method of integrating the operating function of a business. I-D-S reduces the system and programming cost associated with implementing some other types of integrated business systems. It uses direct-access storage as an extension of memory and provides an efficient data organization technique.

Since I-D-S is used to extend the functions of the COBOL language, the reader should have a working knowledge of COBOL before using this manual.

The I-D-S program is identified by catalog numbers CD600H5.100 and CD600H7.000 in the Program Library.

© 1968, 1969, 1970, General Electric Company, U.S.A.
© 1971, Honeywell Information Systems Inc.

Contents

	Page
1. INTRODUCTION	1
2. DATA ORGANIZATION	3
I-D-S CHAINS	4
Multiple Chains	5
STRUCTURE REPRESENTATION	8
SUMMARY OF DATA STRUCTURES	12
Record Classes.	13
I-D-S RECORDS.	14
Linking Detail Records of a Chain	15
Selecting Master Record of a Chain.	15
Chain Ordering.	16
Prime Chain	17
Chain Processing.	17
Chain Tables.	18
3. I-D-S PROGRAMMING LANGUAGE	23
IDENTIFICATION DIVISION.	23
ENVIRONMENT DIVISION	23
Configuration Section, IDS-Special-Names Paragraph.	25
Input-Output Section, File-Control Paragraph.	27
DATA DIVISION.	28
File Description.	28
Complete I-D-S File Description Entry	29
Record Description.	31
Complete I-D-S Record Description Entry	33
Type.	34
Retrieval Via	35
Page-Range.	38
Place Near.	40
Interval.	41
Authority	42
Chain Definition.	43
Complete Chain Definition Entry	44
Master/Detail	45
Chain-Order	47
Linked Prior.	50
Randomize	51
Duplicates.	52

	Page
Ascending/Descending	53
Select	56
Match-Key	57
Synonym	59
Linked-Master	60
PROCEDURE DIVISION	61
I-D-S Imperative Statements	61
Close	62
Debug	63
Delete	64
Go	66
Head	67
Modify	70
Move	72
Open	73
Retrieve	74
Return	77
Sort	79
Store	82
I-D-S Conditional Statements	85
If	86
Perform	88
Use	89
4. TRANSLATOR PROCESSING	91
PAGE EJECT AND COMDK LABELING	91
Page Eject in the Listing	91
COMDK Labeling	91
\$ IDS CONTROL CARD DESCRIPTION	93
SAMPLE OUTPUT PRODUCED BY THE I-D-S TRANSLATOR	95
DECK SETUPS	97
Translate and Compile	97
Translate, Compile, and Execute	98
OBJECT PROGRAM EXECUTION	99
5. I-D-S DATA FILE STRUCTURE DESCRIPTIONS	101
DEFINITION STRUCTURE	101
Communication Control Block	103
Record Definition Entry	104
Detail Definition	107
Master Definition	110
Field Definition	112
Control Definition	114
SAMPLE OUTPUT	116
.QRD - RECORD DEFINITION	120
.QDD - DETAIL DEFINITION	121
.QMD - MASTER DEFINITION	122
.QFD - FIELD DEFINITION	123
.QCD - CONTROL DEFINITION	124

	Page
6. OPERATIONAL CHARACTERISTICS	125
I-D-S DATA FILE INITIALIZATION	125
CREATING AN I-D-S DATA FILE	126
Creating a Permanent I-D-S Data File.	126
Creating a Temporary I-D-S Data File.	129
Mixing Temporary and Permanent Files.	131
ACCESSING AN I-D-S FILE.	132
Subfile Allocation.	132
Subfile Deallocation.	136
I-D-S JOURNAL FILE	136
I-D-S Journal File Configuration.	137
Journal Record Format	137
Closing Journal Files	142
Journal Override.	143
Journal File Map.	144
RECOVERING AN I-D-S DATA FILE.	145
I-D-S EXECUTION REPORT	147
7. MEMORY MANAGEMENT	151
ASSIGNMENT OF I-D-S BUFFERS AND WORK AREAS	151
With a \$ USE Card	151
Without a \$ USE Card.	152
SLAVE I-D-S CONTROL TABLE.	154
Total Control Entry	155
Individual File Entries	156
I-D-S INVENTORY RECORDS.	158
Buffer Format	158
Buffer Strategy for Inventory Buffer.	159
Record Description.	159
I-D-S DATA PAGES	161
Buffer Format	161
Buffer Strategy for Page Buffers.	166
Page Description.	167
I-D-S DATA RECORDS	173
8. I-D-S UTILITY PROGRAMS AND SUBROUTINES	177
PERMANENT I-D-S DATA FILE.	177
TEMPORARY I-D-S DATA FILE.	178
TEMPORARY AND PERMANENT I-D-S DATA FILE.	178
UTILITY PROGRAM AND SUBROUTINE DESCRIPTIONS.	179
Randomizing Analyzer/Calc Pre-Load Sort Utility Program (QUTC)	180
Storage Tape Dump/Print Utility Routine (QUTD).	187
Page Initialize Utility Routine (QUTI).	192
Journal Tape Dump Utility Program (QUTJ).	195
Data Base Load/Print Utility Routine (QUTL)	199
Journal Record Selector Utility Program (QUTP).	206

	Page
Execution Information Report Program (QUTR)	210
Selected Record Sort Utility Program (QUTS)	213
File Utility Program (QUTU)	217
Directive Processor and Service Subroutine (.QDIR) . . .	232
Trace and Print Record, Debug, and Utility Subroutine (.QSTC)	237
Verify and Print Utility Subroutine (.QUTF)	244
 APPENDIX A. RESERVED WORDS	 249
 APPENDIX B. I-D-S ERROR CONDITIONS	 251
 APPENDIX C. GE-600 COBOL/I-D-S/FORTRAN COMMUNICATION AND OVERLAYING	 257
 APPENDIX D. PRIMARY SUBROUTINES	 297
 APPENDIX E. SAMPLE DECK SETUPS	 299
 APPENDIX F. REFERENCE CODE MANIPULATION	 307
 INDEX	 309

Illustrations

Figure		Page
1.	Chain Association	3
2.	I-D-S Chain	5
3.	Master Record of Two Chains	7
4.	I-D-S Shorthand	8
5.	Purchase Order Data Structure	9
6.	Chain Network	11
7.	Legal and Illegal I-D-S Data Structures	12
8.	I-D-S Record.	14
9.	Chain Processing.	18
10.	Chain with Dummy Reference Codes.	19
11.	Chain Table After Retrieval of Detail 2	19
12.	Chain Table Backed Up to Detail 1	20
13.	Chain Table for a PRIOR Processable Chain After Retrieval of Detail 1.	20
14.	Chain Table after Direct Retrieval of Detail 2.	21
15.	Chain Table--PRIOR and HEADED	22
16.	I-D-S Compilation and Execution Process	92
17.	I-D-S Definition Structure.	102
18.	Format of Communication Control Block Entry	103
19.	Format of Record Definition Entry	105
20.	Machine Format for Detail Definition Entry.	107
21.	Machine Format for Master Definition Entry.	110
22.	Machine Format for Field Definition Entry	112
23.	Machine Format for Control Definition Entry	114

Figure		Page
24.	I-D-S Data File Structure	128
25.	I-D-S Data File Allocation.	134
26.	I-D-S Data File Deallocation.	136
27A.	Operational Sequence to Re-establish an I-D-S Data File.	145
27B.	Alternate Operation to Re-establish an I-D-S Data File.	146
28.	Labeled Common .QAREA	153
29.	Slave I-D-S Control Table	154
30.	Inventory Record Buffer	158
31.	Inventory Record.	160
32.	Data Page Buffer.	163
33.	Page Buffer Activity Table.	166
34.	Chain Concept of Buffer Activity.	167
35.	Base Page Header Record	168
36.	Pagette Header Record	171
37.	Data Record	173
38-42.	Sample Output	230
43.	Sample .QSTC Output	243

1. Introduction

Integrated Data Store (I-D-S) is an information-oriented method of integrating the operating functions of a business. Its use reduces the high systems and programming costs associated with implementing some other types of integrated business systems. As a general-purpose system, it uses mass random access storage as an extension of memory and provides an efficient data organization technique. In addition, a simple but effective language is used to operate the system.

Present procedural languages offer programming convenience in field and sequential record processing. However, they are inadequate for processing records in the random environment of mass storage. The I-D-S language provides a simplified means for record processing in the environment of mass random access storage.

Language statements such as those for read/write operations produce serial rather than random actions. Ordinarily, the burden of organizing data records and designing the logic involved in processing and maintaining these records is placed upon the programmer. Many of these processing and maintenance functions are performed automatically by the I-D-S software system.

2. Data Organization

Data organization refers to the interrecord relationships established within the I-D-S data-file. The record is the basic unit of data. Record association is achieved through chains which provide cross-reference linkages between records. These chains provide the integrating force which is implied in the name Integrated Data Store.




Figure 1. Chain Association

I-D-S records are stored only once. Conventional approaches to file organization often require records, or certain fields in the records, to be repeated in several files. With the ability to integrate records into any number of chains (as required by the system), the same data fields are available no matter which of its chains are processed. This technique has five important advantages:

1. Additional space required for duplicate records is eliminated, resulting in a reduction in the total storage capacity required.

2. The work of data maintenance is greatly reduced, as there is only one record to retrieve and modify.
3. The possibility that one copy of a record will not be properly modified is eliminated. Since there is only one copy, any incorrect information will be quickly recognized and corrected.
4. All reports drawn from the file will be consistent, since there is only one set of facts (records).
5. Due to the linking capability, the homogeneity of a file needs no longer to exist and records of different types may be intermixed to achieve a better utilization of the storage capacity.

I-D-S CHAINS

An I-D-S chain is illustrated in Figure 2.

All records in a chain are associated in a closed loop, with the last detail linked back to the master. Its characteristics are:

- Contains one master record and any number of detail records
- Links records together in an endless loop
- Associates related records in meaningful sequences

Records are to be defined by the user as to their relationship within a chain--as master or detail records. These relationships are specified, when the chaining relationship is described, in the data description.

A chain is a set of records that are linked together to form a logical relationship between records.

A Master Record is the head of a set of records that make up a chain. There must be one and only one Master Record for each chain. Detail records are the other records that are members of the set or chain.




Figure 2. I-D-S Chain

Multiple Chains

Chains exist for two separate but closely related reasons. First, the source documentation or problem analysis shows that a portion of the information is often cross-referenced. An example is a personnel record with a variable number of deductions and work experiences.

This kind of information is easily structured by building a personnel master record type. Two chain types are created containing the personnel record as the master record. As many deduction records as necessary are linked into the deduction chain as details. Work experience for the employee involved is handled in a like manner. Both chains are now linked to the same master record, as shown in Figure 3.

The second case involves the logical association of several source documents. Relating all the purchase order information for a given vendor to the vendor information is an example. A purchase order chain associates all of the purchase order records with their vendor record.

I-D-S chains have several structural aspects which should be emphasized:

All similar chains are grouped by chain type.

A chain type is named with a symbolic name. There will be as many chains of the chain type as there are master records for that chain type.

Each chain can have only one master record. Its type is the same for all chains of the same type.

Any number of detail records may be in a chain. A chain may even contain more than one type of detail record.

Detail records cannot be stored unless their master record already exists in the file.

Whenever a master record is deleted, its entire chain is also removed.




Figure 3. Master Record of Two Chains

The master record of the chain contains a code which references the first detail in the chain.

A record may be defined to be a member in as many chains as are required. It may be defined as master in one chain and detail in another.

A record cannot be defined as a detail to itself, directly or indirectly.

As records are stored in the system, they are automatically linked into their defined chains.

When a record is deleted, the chains in which it is a detail record are automatically modified to relink around the deleted record, which will eventually be physically deleted.

STRUCTURE REPRESENTATION

A special graphic technique called I-D-S shorthand has been developed to display records and their chaining relationships.

Its use is particularly important in developing an over-all view when planning a database structure. This technique (see Figure 4) uses a block shape to designate a record type--employee (record type 1) and deduction (record type 2)--and an arrow connecting two blocks to designate a chain type. The arrow points from the master to the detail, as shown in Figure 4.




Figure 4. I-D-S Shorthand

In the foregoing example of I-D-S shorthand, the vertical block-arrow-block sequence carries the following message:

1. There are a number of records in the system of the master type (one for each employee).
2. Each of these records is the master of a chain of the specified type (deduction).
3. There are a number of records of the detail type (deductions 1, 2, 3, 4, etc.) in each such chain.

The purchase order data structure (Figure 5) shows how a vendor record and a particular order record from the example shown in Figure 6 is normally structured in the I-D-S system.




Figure 5. Purchase Order Data Structure

The purchase order contains four groups of information.

1. Information about the vendor--such as his name, address, and vendor code.
2. Information about the order--such as the order number, due date, mode of transportation, and dollar value.
3. Information about the order item--such as delivery date, quantity, unit price, and extended dollar value.
4. Information about the inventory item--such as its identification and description.

The data structure in Figure 5 shows all four groups and their chain associations with only four blocks and three arrows. To expand this structure, four different record types would be designed to carry the information contained in the four groups:

Vendor record--There would be a vendor record for every vendor with whom the business is concerned:

1. It would be the master record of a purchase order chain.
2. Thus, the vendor record is only a master.

Purchase order record--There would be an order record for each order currently stored in the system:

1. It would be a detail in the purchase order chain.
2. Each order, in turn, would be the master of an order item chain.
3. Thus, the purchase order record is both a master and a detail.

Order item record--There would be an order item record for each item on each order:

1. It would be a detail in the inventory on order chain.
2. It would be a detail in the order item chain.
3. Thus, the order item record is a detail in two chains.

Inventory item record--There would be an inventory record for each inventory item currently stored in the system:

It would be the master record of the inventory on order chain.

One expanded data structure concerning Vendor # 34692 for the above records is shown in Figure 6.




Figure 6. Chain Network

SUMMARY OF DATA STRUCTURES

By using I-D-S shorthand, very complex data structures may be presented in a condensed and understandable form. Figure 7 shows a quick summary of data structures which are legal and illegal within I-D-S. A circular definition (item 6), where the master becomes its own detail, is not allowed.




Figure 7. Legal and Illegal I-D-S Data Structures

Record Classes

I-D-S provides three distinct record classes. The designation of the data records as to class is the option of the systems designer and is based on the storage and retrieval requirements of these data records.

I-D-S record processing requires that there be some aspect of every record which makes it unique, or different from any other record. All records are unique by virtue of their reference code. Some records are also unique because they contain one or more data fields--such as a drawing number, order number, and pay number--where no duplicate values are allowed.

CALCULATED RECORDS. Any set of records within the system can be classified as a calculated record. Its storage and retrieval are based upon the contents of one or more data fields. The contents of these fields are externally specified values--such as employee numbers, part numbers, or order numbers. The contents of these fields are processed through a randomizing procedure which determines a page number for an initial storage location. The record is stored on this page. If space is not available on the calculated page, the record is stored on the next successive page with available space. The subsequent retrieval of this record follows this same basic procedure.

SECONDARY RECORDS. Secondary records are unique by their chain relationship to a specified type of master record. The item records associated with a purchase order (master) record are good examples of secondary order records. These records are stored and retrieved by first locating the purchase order record and then stepping through the order item chain to locate the item record by comparison of its item number field.

PRIMARY RECORDS. Records designated in the data description as primary are unique only as a result of their reference codes. Generally primary records are used in place of calculated records where the external assignment of identification fields, such as part number or order number, is not required. In these cases, an internally generated number (the reference code) is assigned and used as the key field for storage and retrieval.

I-D-S RECORDS

The I-D-S record contains a set of data fields which collectively describe the contents of the record. I-D-S augments these records with identification and chain fields (or chain pointers) as shown in Figure 8.




Figure 8. I-D-S Record

There is at least a chain field generated for each chain the record participates in.

The chain fields contain the reference codes of other I-D-S records. They point from one record to the next, creating a circular association of records (see Figure 1).

These associations are automatically processed according to the data descriptions and the procedural commands executed. The arrows in Figure 1 indicate the linking actually carried out through storing the reference code of one record in the body of the prior record.

A reference code is the relative logical (as opposed to physical) address of a data record. It consists of a page number and a line number. The reference code is used by I-D-S to develop and assign a unique address to each data record as it is stored on the mass storage device. Once a record is assigned a reference code, it maintains that reference code until it is physically deleted.

The reference code in its 24-bit binary form is available to the user in a communication area called DIRECT-REFERENCE immediately after the record is stored. For internal use, I-D-S uses a binary number of the form:

XXXXXXXXY

where X is the octal page number and Y is the octal line number.

The page number is a sequential number permanently assigned to each page which defines where in the I-D-S environment the page is stored. It occupies three character positions and permits 262,143 pages per I-D-S file. At execution time page numbers are converted to actual mass storage device addresses by the I-D-S mapping routine.

The line number defines where a record is stored within a page. Line numbers are not sequential within the page because new records are always stored at the end of a page. Line numbers of deleted records are made available for use by new records; the first available line number (the first line number not in use) is assigned to a new record as it is stored into a page. The line number occupies one character and permits 63 line numbers per page.

For example, a reference code (as contained in DIRECT-REFERENCE) of 00010029 decimal becomes 00023455 when converted to octal. This then is page 234 (octal), line 55 (octal).

Linking Detail Records of a Chain

In order to insert a new detail record in a chain, three steps are required:

1. Physical storage space must be found.
2. The appropriate master and its chain must be selected.
3. The record must be inserted in that chain according to the chain ordering rules.

Selecting Master Record of a Chain

There are two rules under which the master record is selected for a new detail record. These are:

1. Select Unique Master--This rule uses the record retrieval criterion, established in the data definition for the master record, to retrieve the particular master record indicated by the data values currently stored in the match control field of Working-Storage.
2. Select Current Master--This rule uses the last record processed, of the master record type, as the master record of the new detail.

Chain Ordering

All chains in the Integrated Data Store system are ordered in one of six methods selected by the system designer with the CHAIN-ORDER clause in the I-D-S language.

The CHAIN-ORDER clause must be used in each Master Chain Definition entry.

The six options of the CHAIN-ORDER clause are:

1. Sorted--With this option all of the records of the chain are maintained in a single sequence regardless of the number of record types in the chain. With this option the same sorting-key(s) must be used to sort the various records.
2. Sorted Within Type--With this option the records of the chain are maintained in sequence within record type, independent of other types.

NOTE: When either of the sorted options is specified, details are added to the chain based upon the contents of the defined sort control fields of the detail records.

3. First--This option causes the detail to be added as the first detail record in the chain relative to the master record.
4. Last--This option causes the detail to be added as the last detail record in the chain relative to the master record.
5. Before--This option causes the insertion of the detail record just before the current record in the chain. This option may be used only in conjunction with the Current Master selection rule.
6. After--This option causes the insertion of the detail record just after the current record of the chain. This option may be used only in conjunction with the Current Master selection rule.

Prime Chain

Access time in present disc-type random access memories varies greatly, since it depends on the position of the desired record relative to the record last accessed. The I-D-S organization of records acknowledges this factor of hardware design and stores new detail records as close as possible to the master record of the chain. When a detail record is specified as a detail in several chains, a prime chain may be chosen and defined by the systems designer preparing the data description. Selection of a prime chain should be based upon an estimate of the most active chain. Thereafter, when an I-D-S page is retrieved which contains the master record of a prime chain, it is highly probable that the detail records of that chain will also be contained in that page or a page closely associated with it. The prime chain is the chain used to retrieve a secondary record by the RETRIEVE command, unless specified otherwise by the data description.

Chain Processing

I-D-S offers complete flexibility in the retrieval of records within a chain by providing three methods of chain inter-linking.

Chain NEXT. The definition of a record as a memory of a chain automatically provides the record with a chain-next field. This is the manner in which all chains are constructed. Each record contains a chain-next field which contains the reference code of the next record in the chain.

Chain PRIOR (optional). I-D-S provides a chain-prior field for all records in a chain when the chain is specified by the system designer as prior processable. This field contains the reference code of the prior record in the chain. This permits the chain to be processed efficiently in a backward direction, as well as forward (through the automatic NEXT chain field).

Chain MASTER (optional). I-D-S provides a chain-master field for all detail records in a chain when specified in the data description. This field contains the reference code of the master record of the chain. Retrieval of the master record is much faster with this ability to address the master record directly from any detail in the chain. Processing need not access all the detail records in the process of seeking the master.

These methods are illustrated in Figure 9.




Figure 9. Chain Processing

Chain Tables

Chain tables are used internally by I-D-S subroutines. A chain table is built by I-D-S for each chain defined. The programmer can reference selective information in the chain table, and a knowledge of what they are and how I-D-S uses them can help in designing efficient chains.

A chain table comprises four entries: MASTER, PRIOR, CURRENT and NEXT. Refer to "Chain Processing" for a description of these entries. As I-D-S traverses a chain, the entries are updated with the reference codes of the data records that are being retrieved.

Figure 10 shows a chain using dummy reference codes.




Figure 10. Chain with Dummy Reference Codes

To interpret the dummy reference codes: master record is 101, detail record 1 is 105, detail record 2 is 205, and detail record 3 is 407.

Assume only the reference code of the master record is known. When I-D-S is asked to get detail record 2 of chain A, I-D-S retrieves the master record of chain A and traverses the chain until the detail record 2 is found. While I-D-S is traversing the chain, it is updating the chain table. When detail record 2 is found, the chain table appears as shown in Figure 11.

Master	101
Prior	105
Current	205
Next	407

Figure 11. Chain Table After Retrieval of Detail 2

Although the chain is not PRIOR processable and is not LINKED TO MASTER, detail 1 is directly available with a RETRIEVE PRIOR OF CHAIN A command. Because of the PRIOR entry in the chain table (in Figure 11), I-D-S would not traverse the chain forward through detail 3, master record, etc., to locate detail 1 but would retrieve it directly at the location stored at the PRIOR entry in the chain table. However, after detail 1 is retrieved by "backing up," the record prior to detail 1 is not known. Therefore, the chain table would now appear as shown in Figure 12.

Master	101
Prior	000
Current	105
Next	205

Figure 12. Chain Table Backed Up to Detail 1

If a RETRIEVE PRIOR OF CHAIN A were executed at this point, I-D-S would have to traverse the chain until it found the PRIOR (in this case, the master) record.

If the chain had been defined as PRIOR processable, the chain table would be updated as shown in Figure 13.

Master	101
Prior	101
Current	105
Next	205

Figure 13. Chain Table for a PRIOR Processable Chain after Retrieval of Detail 1

If a chain were not PRIOR processable, I-D-S could back up one record as though it were PRIOR processable if the prior record in the chain had been passed.

Assume that the reference code of detail 2 is known and the chain is neither HEADED nor PRIOR processable. If a RETRIEVE DIRECT is executed, the chain table is updated as shown in Figure 14.

Master	000	(Unknown)
Prior	000	(Unknown)
Current	205	
Next	407	

Figure 14. Chain Table after Direct Retrieval of Detail 2

Since the chain is neither PRIOR processable nor HEADED (LINKED TO MASTER) and I-D-S did not pass the PRIOR record or the MASTER record in getting to the CURRENT record, I-D-S does not know the reference code of the MASTER or the PRIOR record in this chain. It knows where the NEXT record is because of the chain-next field in detail record 2.

If the chain has been defined as PRIOR processable and HEADED and I-D-S had retrieved detail 2 DIRECT, the chain table would appear as shown in Figure 15.

Master	101
Prior	105
Current	205
Next	407

Figure 15. Chain Table--PRIOR and HEADED

In this case, MASTER and PRIOR references were available from the chain fields in detail record 2.

3. I-D-S Programming Language

The source language of I-D-S is an extension of GE-600 Line COBOL; therefore, formats and language specifications of COBOL must be adhered to when preparing a source program.

IDENTIFICATION DIVISION

The purpose and usage of the Identification Division are identical with those defined for GE-600 Line COBOL, with no special function for I-D-S.

Fixed paragraph names are used as keys in the division. They identify the type of information contained in the paragraph. Paragraphs which may be included in the division are:

IDENTIFICATION DIVISION.
PROGRAM-ID.
AUTHOR.
DATE-WRITTEN.
DATE-COMPILED.
SECURITY.
REMARKS.

ENVIRONMENT DIVISION

All portions of the Environment Division are used as defined by GE-600 Line COBOL, in addition, I-D-S includes the IDS-SPECIAL-NAMES paragraph and the SELECT IDS sentence of the FILE-CONTROL paragraph.

The following illustration is an example of the Environment Division with the use of these two I-D-S functions.

ENVIRONMENT DIVISION.
CONFIGURATION SECTION.
SOURCE-COMPUTER. GE-635.
.
.
.
OBJECT-COMPUTER. GE-635.
.
.
.
IDS-SPECIAL-NAMES.
IDS BLOCK...
.
.
.
INPUT-OUTPUT SECTION.
FILE-CONTROL.
SELECT IDS file-name ASSIGN TO file-code-1.
.
.
.
I-O-CONTROL.
APPLY...
.
.

Configuration Section, IDS-Special-Names Paragraph

Function: To indicate to the I-D-S translator which statements are to be selectively translated. To allow definition of a unique labeled common area for the generated structure of an I-D-S program. To allow RECORD, CHAIN and FIELD names to be included with the generated structure. To indicate to the COBOL compiler all translator generated sections and code are to be suppressed from the COBOL source listing.

Format Option 1:

IDS-SPECIAL-NAMES.

<u>PROCESS</u>	{	<u>ALL</u> LEVEL alpha-1 THRU alpha-2	}	<u>DEBUG STATEMENTS</u>
----------------	---	--	---	-------------------------

Format Option 2:

IDS-SPECIAL-NAMES.

IDS BLOCK integer-1.

Format Option 3:

IDS-SPECIAL-NAMES.

INCLUDE STRUCTURE NAMES.

Format Option 4:

IDS-SPECIAL-NAMES.

APPLY LIST SUPPRESSION

Notes:

1. This paragraph may be omitted when its provisions are not used in the source-program.

2. The PROCESS DEBUG STATEMENTS option is a compiler directing clause that allows the programmer to specify that all or certain selected debugging statements in the source program are to be processed. Debugging statements can be identified by a single character (A-I) in column 7 of the coding form. When the programmer wants all the debugging statements in the source program processed, he specifies this by writing PROCESS ALL DEBUG STATEMENTS. When the programmer wants certain debugging statements processed, he specifies this by writing PROCESS LEVEL alpha-1 DEBUG STATEMENTS. When this is done, only those debugging statements with the specified character (alpha-1) appearing in column 7 are processed.

In addition, the programmer can specify that a range of debugging statements are to be processed by writing PROCESS LEVEL alpha-1 THRU alpha-2 DEBUG STATEMENTS. When this is done, all the debugging statements in the range specified (alpha-1 THRU alpha-2) are processed. Note that when debugging statements identified by a single character in column 7 appear in the source program and the PROCESS DEBUG STATEMENTS option is not included in the source program, those statements with a character in column 7 are unconditionally bypassed (i.e., not processed). The PROCESS ALL DEBUG STATEMENTS option has no effect on statements that have nothing, a hyphen, or an asterisk in column 7.

3. In option 2 the value of integer-1 may be 01 through 99.
4. If Option 2 is used, the labeled common area in which the I-D-S generated structure is assembled will be identified by a symbol of the form "I(integer-1)". If Option 2 is not used, the default symbol for this area will be ".IDS.". (Refer to the GE-600 Line General Loader Reference Manual, CPB-1008, for a discussion of labeled common.)

Example:

IDS-SPECIAL-NAMES.

IDS BLOCK 66.

This would cause the symbol "I66" to be used for the I-D-S generated structure block.

5. Option 3 is used to cause the names of RECORDS, CHAINS and FIELDS to be assembled into the definition structure of the I-D-S-STRUCTURE SECTION.
6. Option 3 will have primary use for programs that use the TRACE and PRINT RECORD, DEBUG, and Utility Subroutine .QSTC, (Chapter 8).
7. Option 4 gives the user the ability to suppress printing of all translator generated coding from the COBOL source listing.
8. The following will be suppressed from the COBOL source listing:
 - a. All I-D-S generated structure within the Working-Storage Section.
 - b. All generated calls to the I-D-S subroutines within the Procedure Division.
 - c. The generated Macro calls within the I-D-S Structure Section.
 - d. All generated tables and constants.
 - e. All generated Enter Definitions.
9. The statements in IDS-SPECIAL-NAMES paragraph may be in any desired order.

Input-Output Section, File-Control Paragraph

Function: To assign an I-D-S file name and to specify the logical device on which it resides.

Format:

FILE-CONTROL.

SELECT IDS file-name ASSIGN TO file-code-1.

Notes:

1. The SELECT IDS entry must be used only once to identify the I-D-S data file.
2. Other optional clauses of the SELECT entry as specified for COBOL should not be used with the SELECT IDS sentence.
3. File-code-1 must be a two-character word consisting of two letters (A,.....,Z) or a letter and a digit (0,.....,9). Each file code must be unique with respect to other file codes in the program.

DATA DIVISION

The description of the I-D-S data file is contained in a special section of the Data Division called the IDS Section. This section must physically follow the Working-Storage Section, if present, and precede the Constant Section.

The IDS Section contains a File Description, Record Description, and Chain Definition as required to describe the complete data file.

The following illustration shows the fixed sections of the Data Division in the order in which they must appear in the source program. A section may be omitted if it is not needed.

Data Division.
File Section.
Working-Storage Section.
IDS Section.
Constant Section.
Report Section.

File Description

The File Description entry provides information regarding the physical characteristics of the I-D-S data file. The entry is used only for documentation purposes and must appear only once in the I-D-S source program and must be the first entry in the IDS Section.

The entry consists of a level indicator, a file name, and a series of clauses which define the physical characteristics of the I-D-S file. The mnemonic level indicator MD is used to identify the start of the File Description entry and to distinguish it from the Record, Field and Chain Descriptions. The format for the complete I-D-S File Description entry follows.

Complete I-D-S File Description Entry

Function: To describe the physical structure of an I-D-S file.

Format:

MD file-name [;PAGE CONTAINS integer-1 CHARACTERS]
[;FILE CONTAINS integer-2 PAGES].

Notes:

1. The file-name must be identical to the one used in the SELECT IDS sentence of the FILE-CONTROL paragraph of the Environment Division.

Other optional phrases of the File Description entry as specified for COBOL do not apply to the IDS Section and must not be used.

2. The PAGE size (integer-1) specified may be any value up to a maximum of 4096 characters. However, the most efficient use of the storage capacity of the mass storage device involved should be considered when establishing the page size.
3. The FILE clause expresses the total physical storage requirements of the I-D-S file. This value must be equivalent to or less than the capacity which has been reserved for the file by the allocation procedure of GECOS. See the GE-600 Line Comprehensive Operating Supervisor (GECOS* III) Reference Manual, CPB-1518, for a discussion of the allocation of permanent random disc or drum files. The maximum number of pages possible within the I-D-S page numbering system is 262,143.
4. Page and file size is for documentation only; it is not used during execution.

*GECOS, Trademark

5. Page and file size clauses are not required.
6. The clauses may appear in any order within the entry. The entry must end with a period.
7. Example:

```
IDS SECTION.  
MD DATA-BASE: PAGE CONTAINS 1920 CHARACTERS;  
FILE CONTAINS 100000 PAGES.  
01 UNIT-MASTER-REC;  
TYPE IS 070;  
RETRIEVAL VIA MASTR FIELD;  
02 MASTR;SIZE 8 NUMERIC.  
98 UNIT CHAIN MASTER;  
CHAIN-ORDER IS SORTED.
```

Record Description

Record Description entries are used to:

1. Provide information to I-D-S regarding the external format of each logical record type as it will exist within a page on the external storage device.
2. Define internal Working-Storage areas which serve as communication interfaces between the user's routine and the I-D-S data file.
3. Provide parameters which control I-D-S processing. These parameters are defined at levels 01 and 98.

The external format of an I-D-S record consists of control fields and data fields. Records are stored as fixed-length records. Each record contains identification fields, a chain field for each chain association specified, and as many characters of data as required by the level 02 entries.

The level 02 entries are packed into the records, and records are packed into pages on a character-oriented basis. Computer word orientation is never used. When a record is retrieved from the storage device, the data fields of the record are available to the user only after they are moved to working storage. Before storing a record, the Working-Storage area must first have been initialized with the data fields of the record to be stored.

The I-D-S Translator creates an internal Working-Storage area for each level 02 entry. The area created may contain subfields which are defined by lower level entries and may be separately referenced by user COBOL procedure statements. However, I-D-S operates only on units of data defined by the level 02 entry. Therefore, any field that is to serve either as a control field or that is to be modified by I-D-S must be defined as a level 02 entry.

The Translator produces parameters from the clauses that are defined at levels 01 and 98. Lower level entries (03-49) may be used to define subfields of the level 02 entry. Any legal COBOL description clause may be used as long as it does not contradict the description provided for the level 02 entry. For a further clarification of the GE-600 Line COBOL Reference Manual, CPB-1652.

The parameters are described in detail on the following pages.

The level 02 data names may not be used for qualification. Qualification of lower level entries up to level 02 is permissible. If the same data name occurs as an 02 entry for different record types, the same Working-Storage area will be shared by the various records involved.

Standard COBOL record description clauses allowed at level 02 are REDEFINES and FILLER. They do not generate Working-Storage areas.

REDEFINES may be used for redefinition of an area previously defined. This enables COBOL procedural statements to reference the Working-Storage area by either of its definitions. The field-oriented functions of I-D-S (MOVE, MODIFY), however, respond only to the original definition of the field.

The use of FILLER as a data-name creates space in the external format only.

Although the PICTURE clause is the significant element of the level 02 description, any of the standard COBOL clauses may be used with the following exceptions:

- OCCURS
- RENAMES
- Editing clauses
- COPY

Complete I-D-S Record Description Entry

Function: To specify the parameters which define an I-D-S record.

Format:

```

01 record-name; TYPE IS integer-1

; RETRIEVAL VIA { field-name
                  { chain-name-1 } FIELD
                  { CALC } CHAIN }

[ ; PAGE-RANGE IS { integer-2 TO integer-3
                  { field-name-1 TO field-name-2 } } ]

[ ; PLACE NEAR chain-name-2 CHAIN ]

[ ; INTERVAL IS integer-4 PAGES ]

[ ; AUTHORITY IS integer-5 ]

```

Notes:

1. Each of the above clauses is applicable only at record level 01.
2. Record-name must be unique, since qualification by file name is not meaningful.
3. The clauses may appear in any order within the entry. The entry must end with a period.
4. All format considerations are as specified for COBOL.

TYPE

Type

Function: To define the Record Type code to be used for reference purposes for each record type within I-D-S.

Format: TYPE IS integer-1

Notes:

1. This clause is required for each level 01 entry.
2. Integer-1 may be any value from 1 to 999.

Retrieval Via

Function: To specify procedures for retrieving and storing a record.

Format:

```

;RETRIEVAL VIA      { field-name
                     { chain-name-1 }
                     { CALC }
                     { FIELD }
                     { CHAIN }

```

Notes:

1. This clause is required for each level 01 entry.
2. Records specified for RETRIEVAL VIA field-name FIELD are referred to as primary records.

Field-name must be defined at level 02 in this record. It must be specified as:

02 field-name PICTURE 9(8).

The field is not stored in the record; it exists only in working storage. The field-name FIELD is called the prime retrieval field.

If the user wishes to retrieve a primary record using the RETRIEVE record-name RECORD statement of the Procedure Division, he must first initialize the field-name with the reference code of the record to be retrieved.

When a primary record is stored, its reference code is placed into DIRECT-REFERENCE. The user may specify the page where he wishes a primary record stored by placing its reference code in the DIRECT-REFERENCE. Zeros may also be stored in DIRECT-REFERENCE which causes the record to be stored on a page most convenient to I-D-S.

Placement of primary records can be modified by the PAGE-RANGE, PLACE NEAR, and INTERVAL clauses.

3. Records specified for RETRIEVAL VIA chain-name-1 CHAIN are referred to as secondary records and are retrieved by their association in the named chain. The chain-name-1 CHAIN is the prime retrieval chain for the record.

When the RETRIEVAL VIA chain-name-1 CHAIN clause is used, the record must be specified at level 98 as chain-name-1 CHAIN DETAIL.

When the RETRIEVE record-name RECORD statement of the Procedure Division is used, the master record of the chain-name-1 CHAIN is first retrieved. Then the specific detail record is found by searching the chain.

If the CHAIN-ORDER is FIRST or LAST, then the RETRIEVAL VIA chain-name CHAIN clause causes the record to be stored on the page of the master record of the chain named in the clause. Otherwise, the record is stored in the page of the current record of the chain named. When a secondary record is stored, I-D-S places its binary reference code into DIRECT-REFERENCE. Placement of secondary records can be modified by PAGE-RANGE, PLACE-NEAR, and INTERVAL clauses.

4. Records specified for RETRIEVAL VIA CALC CHAIN are referred to as calculated records.

RETRIEVAL VIA CALC CHAIN operates the same as RETRIEVAL VIA chain-name-1 CHAIN, except that the master record of the chain is a Page Header record. The CALC CHAIN is called the prime retrieval chain for the record.

When the RETRIEVAL VIA CALC CHAIN clause is used, the record must be specified at level 98 as a CALC CHAIN DETAIL.

When the RETRIEVE record-name RECORD statement of the Procedure Division is used, the Page Header record is first retrieved. Then the specific detail record is found by searching the CALC chain. The Page Header record is found by randomizing the values in the control fields defined in the detail record to be retrieved. The number resulting from the randomization is mapped into the effective page range of the detail record to be retrieved, thereby yielding the page number of the Page Header record whose CALC chain is to be searched.

The RETRIEVAL VIA CALC CHAIN clause causes the record to be stored on the page calculated by randomizing on control fields and mapping into the effective page range of the record.

Placement of calculated records may be modified by the PAGE-RANGE clause. PLACE NEAR and INTERVAL clauses do not apply to calculated records.

5. These three RETRIEVAL procedures provide a basis for classification of each record as one of the following:

- Primary - Retrieved directly via reference code
- Secondary - Retrieved via its chain association
- Calculated - Randomized to the page containing the chain which leads to the record.

Subsequent discussions of I-D-S will refer to records using these terms.

Page-Range

Function: To provide a method for placing various record types within a designated segment of an I-D-S file.

Format: $\left[\text{;PAGE-RANGE IS } \left\{ \begin{array}{l} \text{integer-2 TO integer-3} \\ \text{field-name-1 TO field-name-2} \end{array} \right\} \right]$

Notes:

1. Integer-2 and integer-3 represent the first and last page numbers of a series of pages in which records of a particular type are stored. If integer-2 is greater than integer-3, the series of pages wraps around the end of the file and terminates at a lower page number.

For example, if a 900-page file contained record types A, B, and C, each record type could be isolated in a segment of the file by specifying a page range of 1 to 300 for A, 301 to 600 for B, and 601 to 900 for C.

2. The page numbers must fall within the total number of pages specified for the file.
3. Different types of records may share the same page range.
4. The PAGE-RANGE clause delimits the action of the RETRIEVAL VIA, PLACE NEAR, and INTERVAL clauses.
5. The PAGE-RANGE clause may be used for calculated records.
6. If PAGE-RANGE is not specified, the range is assumed to be equal to the page range of the entire file.
7. If the field name option is used, field-name-1 and field-name-2 must be defined in Working-Storage.

Example:

```
77 field-name-1 PIC 9(6) COMP-1.
77 field-name-2 PIC 9(6) COMP-1.
```

8. The page range values must be placed in field-name-1 and field-name-2 prior to STORE of the record or prior to RETRIEVE of the record.

9. Example:

```
IDS SECTION.
MD DATA-BASE; PAGE CONTAINS 1920 CHARACTERS;
  FILE CONTAINS 100000 PAGES.
01 UNIT-MASTER-REC;
  TYPE IS 070;
  RETRIEVAL VIA MASTR FIELD;
  02 MASTR PICTURE 9(8).
  98 UNIT CHAIN MASTER;
    CHAIN-ORDER IS SORTED.

01 UNIT-REC;
  TYPE IS 010;
  RETRIEVAL VIA CALC CHAIN;
  PAGE RANGE IS 1 TO 20000.
  .
  .
  .
01 QUAD4
  TYPE IS 004
  RETRIEVAL VIA CALC CHAIN
  PAGE-RANGE IS RNG-1 TO RNG-2.
```

PLACE
NEAR

Place Near

Function: To store a record physically near the master record of a specified chain.

Format:

[;PLACE NEAR chain-name-2 CHAIN]

Notes:

1. Chain-name-2 must be a defined chain name. The record to be placed must be specified at level 98 as a detail of the chain named in the PLACE NEAR clause.
2. The PLACE NEAR clause may only be used with primary and secondary records.
3. If the CHAIN-ORDER is SORTED, SORTED WITHIN TYPE, FIRST or LAST, the record is stored on the page of the master record of the chain named in the PLACE-NEAR clause. Otherwise, the record is stored in the page of the current record of the chain.
4. If a current record of the type named exists, the INTERVAL clause supersedes this clause.
5. The PAGE-RANGE clause supersedes this clause when a conflict occurs.
6. Records stored using this clause are subject to the overflow rule.

Interval

Function: To enable uniform distribution of records of a given type across the I-D-S file.

Format:

[;INTERVAL IS integer-4 PAGES]

Notes:

1. Integer-4 represents the number of pages which will be skipped when a record is stored.
2. The INTERVAL clause may only be used with primary and secondary records.
3. Normally, primary records are stored physically according to a reference code furnished by the user. Secondary records are stored physically near the master record of the chain specified in the RETRIEVAL VIA chain-name-1 CHAIN clause or according to a PLACE NEAR clause. When INTERVAL is used, the above criteria apply only to the first record of the stored type. That is, if I-D-S has not processed a record of this type, the CURRENT record value is zero and INTERVAL is not in effect. Subsequent records are stored integer-4 pages away from the current record of the specified type. The current record is either the last record of the type stored or the last record of the type retrieved.

For example, if the last record of type A is stored on page 5 and interval is 3, the next record of type A would be stored on page 8.

4. The INTERVAL clause is used normally for initial file loading of primary master records. By specifying an interval, the user can ensure sufficient space between the master records to store the detail records in their chains.
5. When INTERVAL reaches the end of the page-range or end of the file, it reverts either to the beginning of the page-range or to the beginning of the file.
6. Records stored using this clause are subject to the overflow rule.
7. Application of INTERVAL by I-D-S is not continuous between computer runs. If it is to continue from day to day, it must be reinitialized by retrieving the last record of the type processed in the previous run which makes it current in this run. Storage may continue from this point.

AUTHORITY

Authority

Function: To safeguard data in a record against unauthorized reference or modification.

Format:

[AUTHORITY IS integer-5]

NOTE: Integer-5 may be any value not exceeding 4095(10). The value supplied is used as a lock for data in any record of this type. When this record is referred to during execution, a key must have been supplied that matches the lock. The key is supplied by the OPEN statement which is defined in the Procedure Division.

Chain Definition

A record belongs to at least one, and possibly many chains. A Chain Definition entry must exist for each chain in which the record is included. All Chain Definition entries for a given record must immediately follow the Record Description entries for that record.

The Chain Definition entry consists of a level 98 indicator which names the chain that a level 01 record is either a detail or master in, a chain name, and a series of clauses which define the characteristics of the chain. The complete Chain Definition entry skeleton and a detailed description of the clauses follow.

COMPLETE CHAIN
DEFINITION ENTRY

Complete Chain Definition Entry

Function: To name and describe the interrecord relationship between a master and detail record and to direct the placement of a record into the I-D-S file.

Format Option 1 (Master):

98 chain-name-1 CHAIN MASTER

;CHAIN-ORDER IS {
 SORTED WITHIN TYPE
 SORTED
 FIRST
 LAST
 BEFORE
 AFTER
 }

[;LINKED TO PRIOR]

Format Option 2 (Detail):

98 {chain-name-2} CHAIN DETAIL
 CALC

[;RANDOMIZE ON field-name-1 [;RANDOMIZE...]]

[;DUPLICATES {
 ARE FIRST
 ARE LAST
 NOT ALLOWED
 }]

[; {
 ASCENDING
 DESCENDING
 } KEY IS field-name-2 [; {
 ASCENDING...
 DESCENDING...
 }]]

[;ASCENDING RANGE KEY IS field-name-3]

[;SELECT {
 UNIQUE
 CURRENT
 } MASTER]

[;MATCH-KEY IS field-name-4 [MATCH-KEY...]]

[;MATCH-KEY IS field-name-5 {
 SYNONYM
 SYN
 } field-name-4 [MATCH-KEY...]]

[;LINKED to MASTER]

Master/Detail

Function: To describe a record as either a detail or master of a chain.

Format Option 1:

98 chain-name-1 CHAIN MASTER

Format Option 2:

98 { chain-name-2 } CHAIN DETAIL
CALC

Notes:

1. This entry must be a level 98.
2. Option 1 defines a record as the master record of a chain structure. One option 1 entry is required for each chain structure for which the record is the master. A single chain structure can have only one master record but a single record can be the master of more than one chain structure.

In the example below UNIT-REC is a master record in the SUB-UNIT CHAIN, the ASSIGNMENT CHAIN and the COMPLEMENT CHAIN.

3. Option 2 defines a record as a detail record in a chain structure. One option 2 entry is required for each chain structure in which the record is a detail. A record may be a detail in more than one chain structure. A single chain structure can be made up of any number of detail record types.

In the example below UNIT-REC is a detail record in the CALC CHAIN and the UNIT CHAIN.

4. The record may be a master in one chain structure and a detail in another. In this case, both options are required for that record. A record may not be defined as both MASTER and DETAIL in the same chain.

In the example below, UNIT-REC is a master record in the SUB-UNIT CHAIN, the ASSIGNMENT CHAIN and the COMPLEMENT CHAIN. It is also a detail record in the CALC CHAIN and UNIT CHAIN.

5. If the RETRIEVAL VIA chain-name-1 CHAIN or RETRIEVAL VIA CALC CHAIN clause is used in the level 01 Record Description entry, an option 2 entry must name the appropriate chain structure.

The following statements illustrate this rule:

```
01 SUB-UNIT REC;
    TYPE IS 030;
    RETRIEVAL VIA SUB-UNIT CHAIN;
    PAGE-RANGE IS 1 TO 20000.
02 SUB-UNIT-CODE; SIZE 4 NUMERIC.
98 SUB-UNIT CHAIN DETAIL;
    .
    .
    .
```

6. Example:

```
01 UNIT-REC;
    TYPE IS 010;
    RETRIEVAL VIA CALC CHAIN;
    PAGE RANGE IS 1 TO 20000.
02 UNIT-CODE: SIZE 4 NUMERIC.
    03 DIVISION-CODE: SIZE 1 NUMERIC.
    03 DEPARTMENT-CODE: SIZE 1 NUMERIC.
    03 GROUP-CODE: SIZE 1 NUMERIC.
    03 SECTION-CODE: SIZE 1 NUMERIC.
02 REPORTING-UNIT: SIZE 4 NUMERIC.
02 ORG-NAME: SIZE 20 ALPHANUMERIC.
02 TOTAL-BUDGET: SIZE 7 NUMERIC.
98 CALC CHAIN DETAIL;
    RANDOMIZE UNIT-CODE.
98 SUB-UNIT CHAIN MASTER;
    CHAIN-ORDER IS SORTED.
98 ASSIGNMENT CHAIN MASTER;
    CHAIN-ORDER IS FIRST.
98 COMPLEMENT CHAIN MASTER;
    CHAIN-ORDER IS SORTED.
98 UNIT CHAIN DETAIL;
    SELECT CURRENT MASTER;
    ASCENDING KEY IS UNIT-CODE;
    DUPLICATES NOT ALLOWED.
```

Chain-Order

Function: To specify the criteria for sequencing detail records within a chain.

Format:

CHAIN-ORDER IS { SORTED WITHIN TYPE }
SORTED
FIRST
LAST
BEFORE
AFTER

Notes:


1. This clause must be used in each Master Chain Definition entry (option 1).
2. If either SORTED or SORTED WITHIN TYPE is used, detail records are positioned in the chain according to the value of their sort control fields.

If SORTED is used, the various records of the chain are maintained in a single sequence regardless of the number of record types in the chain. The size and class of sort control fields of the various records must be identical.


If SORTED WITHIN TYPE is used, records of the chain are maintained in sequence within a record type, independent of other types. This does not mean that there is an implied major sort by record type code. It means only that when a given type of record is considered, it is in sequence by its own sort key.

An example of a SORTED and SORTED WITHIN TYPE chain follows.

Sorted Chain



Sorted Within Type Chain



3. The last four forms, `FIRST`, `LAST`, `BEFORE`, and `AFTER`, of this clause cause a detail record to be inserted in the chain relative to some other record in the chain. These options are:

FIRST Insert detail record in chain immediately following the master record.

LAST Insert detail record in chain immediately preceding the master record.

BEFORE Insert detail record in chain immediately preceding the current record of chain.

AFTER Insert detail record in chain immediately following the current record of chain.

The current record of a chain will always be the master record if `SELECT UNIQUE MASTER` has been specified.

The selection of the `BEFORE` and `LAST` Options causes I-D-S to create an extra chain field which contains the reference code of the immediately preceding record of the chain.

`BEFORE` causes the creation of this field in all record types of the chain. `LAST` introduces this field in the master record type only.

The `BEFORE` and `AFTER` forms are compatible only with the `SELECT CURRENT MASTER` clause.

If the chain has been defined as `LINKED TO PRIOR` and the `CHAIN-ORDER IS BEFORE` clause is used, the records in the chain are assigned only one chain field `PRIOR`; there is no duplication of chain fields.

4. When a record is defined as a detail of a calculated chain, no order is maintained because calculated chains have no defined sequence control.

Linked Prior

Function: To provide an additional chain field in each record of a chain which contains the reference code of the immediately preceding record in the chain. This field allows a chain to be traversed in either direction.

Format:

[;LINKED TO PRIOR]

Notes:

1. This clause is used only in the Master Chain Definition entry (option 1). It provides a prior chain field in each record of the chain so that the chain may be traversed in either direction. This feature is especially serviceable when using either the RETRIEVE PRIOR or MODIFY verbs. It also enables the immediate removal of a deleted record which would otherwise stay linked in this chain until the chain was traversed again.
2. Chain PRIOR fields have two disadvantages. First, the record size is increased to provide space for the additional field. Second, the linking process is slower because the chain PRIOR field of the next record must be adjusted when a new record is inserted.
3. When the CHAIN-ORDER IS BEFORE clause is specified, I-D-S automatically provides a chain PRIOR field for all record types defined for that chain.

When the CHAIN-ORDER IS LAST is specified, I-D-S automatically provides a chain PRIOR field for the master record only.

Randomize

Function: To specify those fields of a calculated record used to generate the page number for record placement and retrieval.

Format:

```
[;RANDOMIZE ON field-name-1 [;RANDOMIZE...]]
```

Notes:

1. RANDOMIZE must be used for each calculated record.
2. Field-name-1 must be a level 02 field contained in the record being stored or retrieved.
3. The randomizing routine of I-D-S uses as many fields as are specified.
4. The word RANDOMIZE must precede each control field specified.
5. The fields designated as RANDOMIZE fields are compared at record storage time. An attempt to store a record with identical RANDOMIZE field values will be rejected as an error.
6. This clause may only be used when RETRIEVAL VIA CALC CHAIN is specified at level 01.

DUPLICATES

Duplicates

Function: To specify whether records with identical sort key values may exist in a chain and, if permitted, what ordering action should be taken.

Format:

[;DUPLICATES { ARE FIRST
ARE LAST
NOT ALLOWED }]

Notes:

1. This clause must be used and only used when the chain has been defined as a sorted chain by the CHAIN-ORDER clause.
2. When duplicates are allowed, the new detail may be positioned as the FIRST or LAST of the string of records with identical sort key values.
3. If duplicates are not allowed and an attempt is made to link records with identical sort key values (STORE or MODIFY), an error code is placed in the ERROR-REFERENCE communication area and the duplicate record is rejected.

It is the user's responsibility to examine this communication area.

4. Duplicates are not allowed in a CALC chain; however, it is not necessary to write the DUPLICATES NOT ALLOWED clause. Since CALC chains have no sequence, I-D-S ensures that there are no duplicates by searching the entire CALC chain before attempting to store a new CALC record.

Ascending/Descending

Function: To specify those data fields which control the sequence of detail records in a chain.

Format Option 1:

$$\left[; \left\{ \begin{array}{l} \text{ASCENDING} \\ \text{DESCENDING} \end{array} \right\} \text{KEY IS field-name-2} \left[; \left\{ \begin{array}{l} \text{ASCENDING...} \\ \text{DESCENDING} \end{array} \right\} \right] \right]$$

Format Option 2:

$$\left[; \text{ASCENDING RANGE KEY IS field-name-3} \right]$$

Notes:

1. This clause must be used when a chain has been defined as a SORTED or SORTED WITHIN TYPE chain.

For example: 01 UNIT-MASTER-REC;
 TYPE IS 070;
 RETRIEVAL VIA MASTR FIELD.
 02 MASTR; SIZE 8 NUMERIC.
 98 UNIT CHAIN MASTER;
 CHAIN-ORDER IS SORTED.

01 UNIT-REC;
 TYPE IS 010;
 RETRIEVAL VIA CALC CHAIN;
 PAGE RANGE IS 1 TO 20000.
 02 UNIT-CODE; SIZE 4 NUMERIC.
 02 REPORTING-UNIT; SIZE 4 NUMERIC.
 02 ORG-NAME; SIZE 20 ALPHANUMERIC.
 02 TOTAL-BUDGET; SIZE 7 NUMERIC.
 98 UNIT CHAIN DETAIL;
 ASCENDING KEY IS UNIT-CODE;
 DUPLICATES NOT ALLOWED;
 SELECT UNIQUE MASTER;
 MATCH-KEY IS MASTR.

2. Field-name-2 must be a level 02 field entry within the record being defined. In the above example, UNIT-CODE meets this requirement. However, field-name-2 may not be a level 02 field entry which has been specified at level 01 as a RETRIEVAL VIA field-name FIELD. In the above example MASTR cannot be a KEY.

3. When multiple sort control keys are required to define a chain sequence, the various field-names must be presented in sequence from major control field to minor, thus establishing the sort level of each field. Each sort control key must be independently defined as either ASCENDING or DESCENDING.

When ASCENDING is used, the sorted sequence will be from lowest value of key to highest value.

When DESCENDING is used, the sorted sequence will be from highest value of key to lowest value.


4. Option 2, ASCENDING RANGE KEY is used when the record is to serve as a range master. A range master is a detail record in a sorted chain. In addition, it is the master of a chain which includes detail records falling within the range of the range master. The value contained in field-name-3 controls the ascending sequence of the range masters. It also defines the upper range limit of details referenced by the range master.

Range masters are used primarily to segment long sorted chains. The purpose is to reduce access time in reaching the detail records.


The ASCENDING RANGE KEY clause modifies the search method of the RETRIEVE record-name RECORD and STORE record-name RECORD statements by searching the chain until the sort key value of the retrieved record is equal to or greater than the working-storage value of the record to be retrieved or stored.

If the RANGE option is not specified, the chain is searched until the sort key value of the retrieved record is equal to the working-storage value of the record to be retrieved.

A payroll master chain structure of employee detail records is illustrated below:



By introducing range masters into the structure, the one long chain could be divided into several smaller ones. The structure would look like this:



The steps used to create this structure include:

1. Define Payroll Master record.
 - a. Designate it master record of Payroll-Master chain.
 - b. Designate CHAIN-ORDER as SORTED or SORTED WITHIN TYPE.
2. Define Payroll Range Master record.
 - a. Name within it a field RANGE-NO.
 - b. Designate it as a detail record in the Payroll-Master chain.
 - c. Name RANGE-NO field as an ASCENDING RANGE KEY.
 - d. Designate it master record of Payroll-Range chain.
3. Define Employee Detail record.
 - a. Name within it a field EMPL-NO.
 - b. Designate it as a detail record in Payroll-Range chain.
 - c. Name RANGE-NO as MATCH-KEY for the Payroll-Range chain.
 - d. Name EMPL-NO as a sort key or match-key for this record.


At execute time the user would identify a range master by placing an employee number into RANGE-NO in working-storage. I-D-S selects the first range master in sequence whose value in RANGE-NO is equal to or greater than the value placed in RANGE-NO in working-storage. Once the range master is found, the detail record can be stored or retrieved along its chain by using EMPL-NO as control.

SELECT

Select

Function: To specify the rule for selecting a specific master record from all master records of a given type when a detail record is being stored or retrieved by the RETRIEVE record-name RECORD statement or STORE record-name RECORD statement.

Format:



Notes:

1. One of the two forms of the SELECT clause must be used in each Chain Description entry which specifies a level 98 chain detail. The SELECT clause does not apply to a CALC CHAIN DETAIL because the Page Header record (specified by the output of the randomizing procedure) is the unique master to be selected.
2. When UNIQUE is specified, the master is selected by matching the data field values in a master record with those initialized by the user in working storage. The fields to be initialized are those specified as MATCH-KEY fields in the level 98 entry.
3. When CURRENT is specified, the master of a chain relevant to current detail record of the named chain is selected. If the current record of the named chain is already the master, then it is selected. The responsibility for establishing the current master of the chain-name is left to the user.

Match-Key


Function: To specify those fields which must be initialized by the user in working-storage to allow unique identification of the master record of a chain.

Format:

```
[MATCH-KEY is field-name-4 [;MATCH-KEY...]]
```

Notes:

1. This clause applies only to option 2 of the Chain Definition Entry. It must be used in conjunction with the SELECT UNIQUE MASTER clause.
2. Only those fields necessary to uniquely select the appropriate master need be specified. If the master is a detail record in a higher level chain structure, match-key fields for selection of its master are named with it, but need not be named with this record. For example:



When Master Record B is defined as a detail in Chain A, match-key fields are named for Master Record A. When Detail Record C is defined as a detail in Chain B, match-key fields are named for Master Record B, not for Master Record A.

3. The fields named in MATCH-KEY clauses depend upon the RETRIEVAL clauses specified for each of the higher-level master records defining the hierarchical structure which includes this record as a detail.

The following rules should be used in naming the appropriate master record fields with MATCH-KEY clauses in this record.

If the master record is defined as a primary record by the RETRIEVAL VIA field-name FIELD clause, the field-name must be named as a MATCH-KEY field-name for the detail record.

If the master record is defined as a secondary record by the RETRIEVAL VIA chain-name CHAIN clause, each of the data fields which control the retrieval of the master record must be named as MATCH-KEY field names in this detail record. Thus, it is necessary that the master record be either in a sorted chain (sort keys) or a calculated chain (randomize keys).

If the master record is defined as a calculated record by the RETRIEVAL VIA CALC CHAIN clause, the RANDOMIZE fields for that master must be named as MATCH-KEY fields.

4. All applicable MATCH-KEY fields must be initialized in working storage with the desired values before storing the record or before retrieving it using the RETRIEVE record-name RECORD verb. This includes the match-key fields for all higher level master records involved in the chaining structure even though the fields were not named with this record.

Synonym


Function: To specify an alternate name for a field defined as a MATCH-KEY field.

Format:

```
[;MATCH-KEY IS [field-name-5 {SYNONYM  
SYN}]] field-name-4]
```

Notes:

1. The use of the SYNONYM option within the MATCH-KEY clause defines an alternate name (field-name-5) for the MATCH-KEY field (field-name-4).
2. The alternate name (field-name-5) must have been previously defined in the Working-Storage Section in exactly the same format as the MATCH-KEY field for which it is an alternate.
3. Example:



Detail record type Y is defined in chain structures A and B. Chains A and B have the same record type (X) as their master records. Therefore, each of the two different master records of type X must be uniquely identified when the type Y detail record is stored.

I-D-S stores the detail record into Chain A with one store operation. The master record control field is named with a MATCH-KEY clause when detail Y is defined in both chains. In addition, for Chain B, an alternate working-storage area is named using the SYNONYM clause. Before storing the record, the user must initialize field-name-4 for the master record control field to 100 and the SYNONYM field-name-5 with 200.

LINKED-MASTER

Linked-Master

Function: To provide an extra chain field for each detail record of the chain which points to the master record of the chain.

Format:

[LINKED TO MASTER]

Note:

This optional clause can improve the operation of the system by providing a direct path from each detail to the master of the chain, thus eliminating the need for processing all of the intervening detail records serially.

PROCEDURE DIVISION

Execution of I-D-S procedural statements will STORE, RETRIEVE, MOVE TO WORKING-STORAGE, MODIFY and DELETE records. In addition, these statements will maintain the structure of the data file created by the defined chain relationships.

The communication interface between I-D-S procedural statements and the balance of the COBOL Procedure Division is the working-storage areas which are established for each level 02 field defined in the field description entries of the I-D-S Section. All COBOL references to data from the I-D-S file are to these working-storage areas.

The procedural statements of I-D-S may appear anywhere in the context of the COBOL Procedure Division. An I-D-S sentence must be preceded by ENTER IDS and terminated by a period. The sentence may contain any number of I-D-S statements. A paragraph name or section name may be assigned to an I-D-S sentence in a manner consistent with normal COBOL format.

The following pages describe these various statement and verb formats.

I-D-S Imperative Statements

The imperative statements included in this section are provided as a part of the I-D-S language to extend the function of the basic STORE and RETRIEVE verbs. The DELETE, HEAD, MODIFY and MOVE statements apply only to the RETRIEVE verb; the DEBUG and GO statements may be used with either verb. OPEN must be used prior to any other I-D-S statements; CLOSE is self-explanatory.

When these statements are used, they must occur in the order in which they are to be executed. They may be contained within the sentence beginning with the basic verb and ending with a period, or they may be used as separate sentences preceded by ENTER IDS.

The specific formats of these statements and detailed discussions of the restrictions and limitations associated with each appear on the following pages.

CLOSE

Close

Function: To transfer all modified I-D-S pages currently residing in the core buffers to the mass storage unit.

Format OPTION 1:

CLOSE

Format OPTION 2:

CLOSE WITH LOCK

Notes:

1. This statement must be executed before any COBOL STOP RUN statement. No automatic closing takes place.
2. OPTION 2 will insure that the data base cannot be opened again during the execution of the run unit.
3. See (Chapter 6, Accessing an I-D-S File) for Sample Deck set up.

Debug

Function: To permit the selective dumping of pages, records, current data of program chain tables, or records of chain. The output produced will appear on the system execution report.

Format:

DEBUG CURRENT $\left[\left\{ \begin{array}{l} \text{BUFFER} \\ \text{RECORD} \\ \text{CCBLOC} \end{array} \right\} \left[; \left\{ \begin{array}{l} \text{BUFFER} \\ \text{RECORD...} \\ \text{CCBLOC} \end{array} \right\} \right] \right]$

and $\left[; \text{chain-name-2 CHAIN} \right]$

$\left[; \text{TRACE chain-name-3 CHAIN} \right]$

Notes:

- Chain-name-2 and chain-name-3 must be names of chains as defined by level 98 entries in the IDS Section of the Data Division.
- The BUFFER option will result in an octal/BCD printout of the current page of the I-D-S data file.
- The RECORD option will result in an octal/BCD printout of the logical record last accessed by a successful STORE or RETRIEVE verb.
- The CCBLOC option will result in a printout of the following format:

DIRECT REFERENCE	<u>Ref. Code in octal</u>	<u>Ref. Code in BCD</u>
FIRST REFERENCE	<u>Ref. Code in octal</u>	<u>Ref. Code in BCD</u>
LAST REFERENCE	<u>Ref. Code in octal</u>	<u>Ref. Code in BCD</u>
RECORD TYPE	<u>Rec. Type in octal</u>	<u>Rec. Type in BCD</u>
ERROR REFERENCE		<u>Error Code in BCD</u>

- The chain-name-2 CHAIN clause will result in an octal/BCD printout of the reference codes of the named chain as follows:

CHAIN TABLE HEAD	<u>Ref. Code in octal</u>	<u>Ref. Code in BCD</u>
CHAIN TABLE PRIOR	<u>Ref. Code in octal</u>	<u>Ref. Code in BCD</u>
CHAIN TABLE CURRENT	<u>Ref. Code in octal</u>	<u>Ref. Code in BCD</u>
CHAIN TABLE NEXT	<u>Ref. Code in octal</u>	<u>Ref. Code in BCD</u>

- The TRACE chain-name-3 CHAIN clause will result in a side-by-side octal/BCD printout of all of the records contained within the specified chain.

DELETE

Delete

Function: To delete the current record of the program and remove it from all chains in which it is a detail to make the record unavailable for processing and, optionally, to perform certain functions when specified detail record types are accessed during the deletion process.

Format:

```
;DELETE [CURRENT record-name-1 RECORD [ON record-name-2 DETAIL  
        [MOVE TO WORKING-STORAGE]  
        [HEAD chain-name-1 CHAIN [HEAD...]]  
        [PERFORM procedure-name-1]  
        [GO TO procedure-name-2]]]  
        [ { OTHERWISE } ON record-name-3 DETAIL...  
          [ ELSE ] ] ]
```

Notes:

1. The record deleted by the DELETE statement is the record last retrieved (CURRENT) by the RETRIEVE verb.
2. The deletion process deletes a record only when there are no dependent details in its chains. When details are present, the system first attempts to delete the dependent detail records. Since the hierarchical data structure of I-D-S may involve many levels of detail records, this statement should be used with care.
3. The execution of a DELETE statement makes the record retrieved unavailable for any further processing, and an attempt to reference such a record results in an error condition.

4. The conditional statement ON record-name-2 DETAIL is used only when it is necessary to interrupt the deletion process when a dependent detail of the type named by record-name-2 is encountered. When the statement is used, various imperative statements immediately following are executed prior to the actual deletion of the detail record. After the execution of these statements, the deletion process is continued unless one of the statements was a GO TO statement. In this case, control is not returned to the deletion process. When the record encountered is not the type named by record-name-2 it is compared with the type named by record-name-3. The reserved words OTHERWISE or ELSE separate the tests for different record types that may be encountered. A record encountered which does not match any of the specified record types is deleted in the normal manner.
5. As a record is deleted it is not implicitly moved to working storage.
6. The CURRENT record-name-1 RECORD option causes the record type of the record named to be compared with the record type in the current record definition. If they are not equal, an error code (R10) is returned to the user and no deletion takes place.

GO

Go

Function: To depart from the normal in-line sequence of procedures.

Format:

;GO TO procedure-name-1

Notes:

1. Procedure-name-1 may be any COBOL or I-D-S procedural paragraph in the Procedure Division.
2. When this statement is encountered within the I-D-S sentence, all subsequent statements are bypassed and control is transferred to the procedure named.
3. GO TO may be used with:
 - If ERROR...
 - If record-name...
 - ON record-name DETAIL...
4. GO TO must be used with:
 - RETRIEVE EACH AT END...

Head


Function: To retrieve the master record of the chain specified and to move its data fields to working storage making it available for processing.

Format:

`;HEAD chain-name-1 CHAIN [;HEAD...]`

Notes:

1. The chain-name-1 must be a chain defined by a level 98 entry.
2. If no records of this named chain have been processed, or if the last record has been deleted, an error condition is noted.
3. A data structure in I-D-S shorthand is shown below.



In this case, assume that REC-AA was the record initially retrieved by the RETRIEVE verb. At this point, three chains include REC-AA, therefore, three possible master records may be referenced by the HEAD statement. Notice, however, that once HEAD has been used to reference CHAIN-A, the next higher level CHAIN-A1 can be referenced.

4. This statement includes an implied move of the record retrieved to working storage.
5. After execution of this statement, the master records retrieved are the CURRENT records of their respective types. They become the CURRENT records in each chain in which they are defined as details. However, they are not the CURRENT records in chains in which they are defined as master records. In those chains, the detail record which leads to the master is the CURRENT record.
6. Note that the function of the statement is very similar to that of the RETRIEVE MASTER RECORD statement, except for the manner in which CURRENT of chain is maintained (Note 5).
7. Example:

Assume chains X, Y, A, and A1 are not PRIOR processable or HEADED (linked to MASTER). The chain tables show REC-AA after it has been retrieved via chain-X and before execution of the HEAD CHAIN-A CHAIN statement. Note that there is a chain table for each chain in which REC-AA is a detail record.

REC-AA Chain-X		REC-AA Chain-Y		REC-AA Chain-A	
MASTER	REC-XR	MASTER	Unknown	MASTER	Unknown
PRIOR	REC-AA-1	PRIOR	Unknown	PRIOR	Unknown
CURRENT	REC-AA	CURRENT	REC-AA	CURRENT	REC-AA
NEXT	REC-AA+1	NEXT	REC-AA+1	NEXT	REC-AA+1

After execution of the HEAD CHAIN-A CHAIN statement, the chain tables appear as shown below. Note that the chain tables for chains X and Y remain unchanged. The only change to the chain-A table is that the chain table's MASTER position has been updated with the reference code of the master record. Thus, if a RETRIEVE NEXT or PRIOR of chain X, Y, or A is issued, REC-AA is the CURRENT record from which I-D-S moves to the NEXT or PRIOR data record of chain X, Y, or A.

REC-AA
Chain-X

MASTER	REC-XR
PRIOR	REC-AA-1
CURRENT	REC-AA
NEXT	REC-AA+1

REC-AA
Chain-Y

MASTER	Unknown
PRIOR	Unknown
CURRENT	REC-AA
NEXT	REC-AA+1

REC-AA
Chain-A

MASTER	REC-AB
PRIOR	Unknown
CURRENT	REC-AA
NEXT	REC-AA+1

After the HEAD CHAIN-A CHAIN statement is executed, the chain A1 table is updated as shown below.

REC-AB
Chain-A1

MASTER	Unknown
PRIOR	Unknown
CURRENT	REC-AB
NEXT	REC-AB+1

MODIFY

Modify

Function: To modify the contents of all or selected fields of the current record and/or to relink any chain which may be affected by the modification of a control field.

Format Option 1:

```
;MODIFY field-name-1 [field-name-2...]
```

Format Option 2:

```
;MODIFY CURRENT record-name [field-name-1 [field-name-2...]]
```

Notes Option 1:

1. The fields to be modified must be level 02 entries. The contents of working storage are moved to the equivalent field of the current record which is in a data page buffer.
2. Field-name-1, field-name-2, may be control fields for the record. Modifying these fields can result in the record being logically repositioned within the I-D-S environment. Depending on the type of control field involved, I-D-S will take the following actions:

Modifying a sort key field. The record is relinked into its chain according to the new value of the sort field. The sort field in the record is then modified.

Modifying a randomize field. The record is relinked into a new CALC chain according to the new value of the randomize field. The randomize field in the record is then modified.

3. In relinking a record in a chain, I-D-S uses all the control fields in working storage defined in the record for that chain. Therefore, the user must not only initialize the control field to be modified, but the others as well. Depending upon the control fields involved, I-D-S will take the following action:

Modifying a match-key field named to uniquely identify a master record. The record is relinked to the new master uniquely identified by the new value in the match-key field. Since the field is not in the detail record, no actual field modify occurs.

Modifying field-name-5 of a MATCH-KEY IS field-name-5 SYNONYM field-name-4 clause. The record is relinked to a new master record along the chain for which the clause was named. The new master was uniquely identified by the new value in field-name-5. In this case, field-name-5 may or may not be a field in the record on disc. If it is, it is modified. If it is not, no further action is taken.

4. In no case is a record ever physically moved from one page to another in the I-D-S environment. Therefore, an attempt to modify the prime retrieval field of a primary record results in an error condition. Such a modify could result in a record needing to be moved from one page to another.
5. If the successful execution of the MODIFY statement would create DUPLICATE records in chains where they are not allowed, the modification will not be executed and an error occurs.

Notes Option 2:

1. Notes for option 1 also apply to option 2.
2. The record type of the record named is compared with the record type in the current record definition. If they are not equal, an R11 error code is returned to the user and no modification takes place.
3. If the field name option is not specified, all fields in the record are modified.

MOVE

Move

Function: To move all or selected fields of the current record (record last processed) to working storage, or to move the contents of a chain table to working storage.

Format Option 1:

```
;MOVE TO WORKING-STORAGE [field-name-1 [,field-name-2...]]
```

Format Option 2:

```
MOVE chain-name-1 { CHAIN TABLE  
MASTER  
PRIOR  
CURRENT  
NEXT } TO field-name-3
```

Notes:

- 1. The implied source of an option 1 MOVE is the current record (last RETRIEVE or STORE).
2. Option 1 must be used before any reference can be made to the data in the record.
3. When the statement includes the list of fields identified by field-name-1, field-name-2, etc., only those fields are moved to working storage. Otherwise, all fields are moved.
4. When CHAIN TABLE is used in option 2, the master, prior, current, and next chain fields of the named chain are moved to four contiguous subfields specified by field-name-3. Field-name-3 should be equivalent to the form:

```
01 field-name-3
02 Master-chain PICTURE 9(6) COMP-1
02 Prior-chain PICTURE 9(6) COMP-1
02 Current-chain PICTURE 9(6) COMP-1
02 Next-chain PICTURE 9(6) COMP-1
```

- 5. When MASTER, PRIOR, CURRENT, or NEXT is used in option 2, the specified chain-table entry is moved to field-name-3. Field-name-3 should be equivalent to the form:


```
02 field-name-3 PICTURE 9(6) COMP-1
```


RETRIEVE

Retrieve

Function: To retrieve a record and make it available for processing.

Format Option 1:



Format Option 2:

RETRIEVE NEXT RECORD OF CALC CHAIN

Notes:

1. Record-name-1 must be the name of the record level 01 entry defined in the IDS Section of the Data Division.
2. Chain-name-2 must be the name of a chain defined by a level 98 entry in the IDS Section of the Data Division.
3. Regardless of the option used, this verb causes the record referenced to be retrieved and made available in the memory buffer. This action may or may not require that a page be transmitted from the mass storage device, since the record may already be in memory. No other action, such as moving the record to working storage takes place.

The reference code of the record retrieved is accessible in the communication cell named DIRECT-REFERENCE after the retrieval process is completed.

4. Of the seven options available with the RETRIEVE verb, two may be classified as absolute. This means that only one record will satisfy the retrieval specification when one of the following options is used.

RETRIEVE record-name-1 RECORD

The record retrieval action is predicated upon the RETRIEVAL VIA clause defined in the level 01 entry in the IDS Section of the Data Division. The record retrieved depends on the values contained in the control fields of working storage which uniquely identify the record.

If the record is retrieved VIA field-name FIELD, the contents of the named field (the reference code of the record to be retrieved) are used.

If the record is retrieved VIA CALC CHAIN, the contents of the RANDOMIZE fields are used.

If the record is retrieved VIA chain-name CHAIN, the contents of its MATCH-KEY and ASCENDING and DESCENDING sort key fields are used.

RETRIEVE DIRECT

The record to be retrieved is identified by the reference code stored in a communication cell named DIRECT-REFERENCE. The user is responsible for initializing the communication cell prior to the execution of this command.

The other five options may be classified as context dependent, since the actual record retrieved is dependent upon previous record processing.

RETRIEVE CURRENT record-name-1 RECORD

The record retrieved will be the current record of record-name-1 specified. If no record of this name has been processed, or if the last record processed has been deleted, an error condition is noted.

RETRIEVE $\left\{ \begin{array}{l} \text{NEXT} \\ \text{PRIOR} \\ \text{MASTER} \end{array} \right\}$ RECORD OF chain-name-2 CHAIN

Record retrieval depends upon the current record of the chain named. If NEXT or PRIOR is used, the appropriate record is retrieved regardless of the record type. If MASTER is specified, the master record of the chain named is retrieved. If no records of the chain have been processed, or if the last record has been deleted, such that no records exist in the chain, an error condition is noted.

RETRIEVE EACH AT END GO TO procedure-name-1

This option facilitates a reference code ascending sequence serial search of the I-D-S data file. This statement will retrieve the first record, in ascending reference code sequence, that has a reference code value equal to or greater than the reference code value stored in the FIRST-REFERENCE communication cell named. However, if the reference code value of the retrieved record is equal to or greater than the value stored in the communication cell named LAST-REFERENCE, control is transferred to procedure-name-1.

When a record is retrieved, the sum of its reference code value plus one will be stored in FIRST-REFERENCE, which initializes it for a subsequent execution of RETRIEVE EACH.

5. An option 2 entry record retrieval depends on the CURRENT record within the chain specified. If NEXT is used, the appropriate record is retrieved regardless of the record type. These record specifiers can be used only if some record has already been processed which is a member of the CALC chain.
6. If a record cannot be retrieved according to the specifications of the retrieval statement, an error condition is noted.
7. The record retrieved is recorded as the CURRENT record of its type and the CURRENT record in each chain in which it is a master or detail.
8. Example:

The following statements will retrieve the master and detail records of the calc chain. The master of the calc chain is the Page Header record.

```
    COMPUTE DIRECT-REFERENCE = page-number * 64.  
ENTER IDS.  
    RETRIEVE DIRECT    (master of calc chain)  
        IF ERROR ...  
    RETRIEVE NEXT of CALC chain.  
        IF RECORD-TYPE = 1000 GO TO end-chain.
```

Return

Function: To relink the selected records of a specific chain into the order as returned by the sort. To return the data fields of the I-D-S record to Working-Storage.

Format:

```
RETURN chain-name-1 CHAIN  
AT END GO TO procedure-name-1
```

Notes:

1. RETURN can only be used within an OUTPUT PROCEDURE associated with a SORT statement for sort-file-1. Any other use of a RETURN statement will lead to unpredictable results at object execution time.
2. The execution of the RETURN statement causes the next record in sorted order (according to the keys listed in the SORT statement) to control the retrieval of the corresponding I-D-S record in chain-name-1. The I-D-S record is then relinked into its ordered position in chain-name-1 as though the CHAIN-ORDER is described as AFTER. The chain will appear as: MASTER, 1st record from sort, 2nd record from sort, etc.
3. The data fields of the sorted selected I-D-S record will be moved to the I-D-S working-storage fields. The record returned from sort will not be available for processing in the record area associated with sort-file-1.
4. The I-D-S record will be current of program, current of type, and current of chain-name-1. The record will not be current in any other chains in which it participates.

5. Example:

```
FILE SECTION.  
SD ST-FILE.  
  DATA RECORD IS SORTR.  
  01 SORTR.  
    02 PRIOR-REF      PIC 9(6) COMP-1.  
    02 CUR-REF        PIC 9(6) COMP-1.  
    02 KEY-1 PIC      9999.  
    02 KEY-2 PIC      999999.  
  .  
  .  
  .  
SORT-CALL SECTION.  
SORT ST-FILE ON ASCENDING KEY KEY-1, KEY-2.  
  INPUT PROCEDURE IS PHASE-1.  
  OUTPUT PROCEDURE IS PHASE-2.  
  .  
  .  
  .  
ENTER IDS.  
  RETURN TST-CHAIN CHAIN  
  AT END GO TO PHASE-2X.  
  .  
  .  
  .
```

Sort

Function: To sort the selected records of a specific chain into the specified order.

Format:

```
SORT sort-file-1 ON { ASCENDING } KEY field-name-1
                   { DESCENDING }
[ ,field-name-2... ] [ ;ON { ASCENDING } KEY ...
                    { DESCENDING } ]
{ INPUT PROCEDURE IS section-name-1 [ THRU section-name-2 ] }
{ USING file-name-2 }
GIVING chain-name-1 CHAIN
```

Notes:

- 1 The COBOL SORT is used to accomplish the sort of the selected I-D-S records.
2. All rules of COBOL SORT must be observed. The I-D-S exceptions are discussed in the following notes.
3. The sort-file-1 Record Description must be equivalent to the form:

```
01 SORT-IDS-REC.
```

```
    02 Prior-ref    PIC 9(6) COMP-1.
```

```
    02 Current-ref  PIC 9(6) COMP-1.
```

```
    02 Sort-key-1.
```

```
    .
    .
    .
```

The prior-ref field must be the first entry in the sort record.

The current-ref field must be the second entry in the sort record.

4. The INPUT PROCEDURE must:
 - RETRIEVE the I-D-S records from the specific chain.
 - MOVE the PRIOR reference or zero to the prior-ref field.
 - MOVE the CURRENT reference to the current-ref field.
 - MOVE the data fields into the sort KEYS. (Other data may be placed in the sort record; however, I-D-S will not make use of the data.)
 - RELEASE the sort record.
5. The GIVING chain-name-1 CHAIN clause means that all sorted records in sort-file-1 are used during the relink process to control the retrieval of the corresponding I-D-S record in chain-name-1. The I-D-S records are relinked into chain-name-1 as though the CHAIN-ORDER is described as AFTER. The chain will appear as MASTER, 1st record from sort, 2nd record from sort, etc.
6. If the prior-ref field is set to zero the execution of the relink function may be inefficient.
7. The chain may contain multiple record types. If only one type of record is selected for sorting, the selected sorted records will appear in order following the master record. The remaining record types will retain their relative order in the chain after all of the selected sorted records.
8. The USING file-name-2 option requires file-name-2 to be of the described format. The records must be equivalent to records which would result by using the INPUT PROCEDURE option. All records must be present in the selected chain.
9. At the completion of SORT the last record in the sort sequence will be current of program, current of type, current of chain-name-1, and its data fields will be moved to the I-D-S working-storage fields. It will not be current in any other chains in which it participates.

10. Example:

```
FILE SECTION.  
SD ST-FILE.  
  DATA RECORD IS SORTR.  
  01 SORTR.  
    02 PRIOR-REF      PIC 9(6) COMP-1  
    02 CUR-REF        PIC 9(6) COMP-1.  
    02 KEY-1  PIC      9999.  
    02 KEY-2  PIC      999999.  
  .  
  .  
  .  
SORT-CALL SECTION.  
ENTER IDS.  
SORT ST-FILE ON ASCENDING KEY KEY-1, KEY-2  
  INPUT PROCEDURE IS PHASE-1  
  GIVING TST-CHAIN CHAIN.  
  .  
  .  
  .  
ENTER IDS.  
  RETRIEVE MSTR.  
LOOPA.  
ENTER IDS.  
  RETRIEVE NEXT TST-CHAIN CHAIN.  
ENTER IDS.  
  IF MSTR RECORD GO TO P1LAST.  
ENTER IDS.  
  IF DET-2 RECORD GO TO LOOPA.  
ENTER IDS.  
  MOVE.  
  MOVE FIELDA1 TO KEY-2.  
  MOVE FIELDB1 TO KEY-1.  
ENTER IDS.  
  MOVE TST-CHAIN PRIOR TO PRIOR-REF.  
ENTER IDS.  
  MOVE TST-CHAIN CURRENT TO CUR-REF.  
  .  
  .  
  .
```

STORE

Store

Function: To place a record into the I-D-S data file, to establish any chain fields which have been defined, and to make the record available for processing.

Format:

STORE record-name-1 RECORD

Notes:

1. Record-name-1 must be defined as a level 01 entry in the IDS Section of the Data Division.
2. When this verb is used, the following is assumed:

Working-Storage for this record has been initialized with the data contents for the record.

Any other control fields required to provide unique identification of the master records of the defined chains which include record-name-1 have been initialized in their respective working-storage areas.
3. The record is placed into the file as defined by the PLACE NEAR or RETRIEVAL VIA clauses of the Record Description entry.
4. The reference code assigned to the record is left in the communication cell DIRECT-REFERENCE after the storage process is complete.
5. The record is recorded as the CURRENT record of its type and the CURRENT record in each chain in which it is a master or detail.
6. If the storage process creates a duplicate record in violation to any DUPLICATES NOT ALLOWED clause, or if the unique or range master selected cannot be retrieved, the storage process is terminated with all linkages restored as before and an error condition is noted.
7. When a primary record is stored, its reference code is moved to the working-storage field named by the RETRIEVAL VIA field-name FIELD clause.

8. Placement of records by I-D-S is influenced by the RETRIEVAL VIA, PAGE-RANGE, PLACE NEAR, and INTERVAL Clauses. The following summaries show priority of record storage criteria. If PAGE-RANGE is specified and the resultant page number falls outside the page range, the page number is always scaled down to fall within the page range.
9. Primary records are stored as follows:
 - a. If INTERVAL is specified and the current page is not zero, on the page calculated by INTERVAL plus page of current record of the type.
 - b. If not as a, above, on the page specified in DIRECT-REFERENCE, if it is not zero.
 - c. If not as a or b, above, and if PLACE NEAR is specified and the CHAIN-ORDER is SORTED, SORTED WITHIN TYPE, FIRST, or LAST, on the page of the master record of the chain named in the PLACE clause.
 - d. If not a, b, or c, above, on the page of the current record of the chain-name.
 - e. If none of the above, on a page most convenient to I-D-S.
10. Secondary records are stored as follows:
 - a. If INTERVAL is specified and the current page is not zero, on the page calculated by INTERVAL plus page of current record of the type.
 - b. If not as a, above, and if PLACE NEAR is specified and the CHAIN-ORDER is SORTED, SORTED WITHIN TYPE, FIRST, or LAST, on the page of the master record of the chain named in the PLACE clause.
 - c. If not as a or b, above, on the page of the current record of the chain-name.
 - d. If not as a, b, or c, above, and if the CHAIN-ORDER of the RETRIEVAL VIA chain is SORTED, SORTED WITHIN TYPE, FIRST or LAST, on the page of the master record of the chain named in the RETRIEVAL VIA chain-name CHAIN clause.
 - e. If none of the above, on the PAGE of the current record of the RETRIEVAL VIA chain.

11. Calculated records are stored as follows:

On the page calculated by randomizing the contents of fields named in the RANDOMIZE ON field-name clause.

12. Record storage is subject to the following Overflow rule:

If space is not available in the specified page, the record is placed on the first page in the direction of ascending page numbers in which there is available space as determined by search of the inventory records. Pages which do not have inventory records are bypassed until all pages controlled by inventory are searched. If space is not found by the inventory search, then all pages not controlled by inventory are searched. The boundaries specified by the use of a PAGE-RANGE clause are observed in this process.

I-D-S Conditional Statements

The conditional statements of I-D-S are logical extension of the basic STORE and RETRIEVE verbs. Generally, they involve the key word IF, followed by the condition to be tested, followed by the imperative statements to be performed.

I-D-S conditional statements are of two general forms; either form may appear in the string of statements following a basic verb.

The specific formats of these statements and a discussion of their restrictions and limitations follow.

Following the explanation of the IF-clause formats, PERFORM and USE, which also are conditional, are discussed.

IF

If

Function: To conditionally transfer control to an alternate procedure.

Format Option 1:

```
      ;IF record-name-1 RECORD  statement-1  [;statement-2...]  
      {  
      OTHERWISE  
      ELSE  
      } statement-3  [;statement-4...]
```

Format Option 2:

```
      ;IF ERROR statement-1 {  
      OTHERWISE  
      ELSE  
      } statement-2 [;statement-3...]
```

Notes Option 1:

1. The IF record-name-1 RECORD clause is specifically designed to support those retrieval statements where the type of record to be retrieved is unknown until after the retrieval is complete. Specifically, the IF record-name clause may only be used in conjunction with RETRIEVE DIRECT, RETRIEVE EACH, RETRIEVE NEXT and RETRIEVE PRIOR.
2. Statement-1, 2, 3, 4 may be any one of the following statements: MOVE TO WORKING-STORAGE, MODIFY, DELETE, HEAD, PERFORM, or GO TO. In addition, statement-3 may be another IF record-name clause. This allows multiple test-branch logic based on record type.
3. The record type field in the record just retrieved is compared with the record type named by record-name-1. If the record types are the same, statement-1 and subsequent statement-2's are executed in sequence and then control is transferred to the next sentence in the program. A GO TO procedure-name statement may be used as either statement-1 or statement-2 to cause a transfer to some alternate sentence in the program.

If the record retrieved is not the type specified, then control is transferred around statement-1 and subsequent statement-2's to statement-3, or to the next sentence in the absence of an OTHERWISE or ELSE phrase.

Notes Option 2:

1. This form may only follow a STORE or RETRIEVE verb or a MODIFY, DELETE, HEAD, or MOVE imperative statement.
2. Statement-1 may only be a GO TO or a PERFORM imperative. Statement-2, statement-3, etc., may be any imperative statement appropriate to the basic verb, or a conditional of form 1, if appropriate.
3. The IF ERROR clause tests the occurrence of any logical error as a result of the last I-D-S statement. The specific errors which may occur are a function of the statement executed. The user program may determine the type of error by referring to the ERROR-REFERENCE communication cell.
4. If an error occurs because of hardware, data description, or improper use of an I-D-S function, the program is brought to an orderly halt, the file closed and the program aborted and memory dumped, if requested, with the appropriate error message.
5. If a data-dependent error is detected by I-D-S, an error code will be stored in ERROR-REFERENCE and control will pass to the IF ERROR STATEMENT.
6. The execution of a subsequent I-D-S statement will reset the error code stored in ERROR-REFERENCE.

PERFORM

Perform

Function: To depart from the normal in-line sequence of procedures in order to execute a specific procedure and then return to the normal sequence.

Format:

PERFORM procedure-name-1 [THRU procedure-name-2]

Notes:

1. Procedure-name-1 may be any COBOL procedural paragraph in the Procedure Division.
2. For other details concerning the PERFORM statement see the GE-600 Line COBOL Reference Manual, CPB-1652. Only the simple PERFORM (option 1) is recognized within an I-D-S sentence.
3. PERFORM may be used with:
 - IF ERROR...
 - IF record-name...
 - ON record-name DETAIL...
4. If PERFORM is used with ON record-name DETAIL, the procedure performed may not contain any I-D-S functions. The THRU procedure-name-2 may not be used.

Use

Function: To specify procedures to be executed for I-D-S error conditions which are in addition to the standard procedures supplied by I-D-S.

Format:

```
USE procedure-name-1 [THRU procedure-name-2]
  [WITH TRACE]
  ON { error-code-1 [ , error-code-2... ] .
      ANY ABORT }
```

Notes:

1. The USE clause may appear anywhere within the Procedure Division.
2. The procedures specified will be executed by COBOL PERFORM.
3. The procedures may not contain I-D-S statements. The activity will be aborted if any I-D-S statements are executed while the USE procedures are being performed.
4. The I-D-S error codes used as error-code-1 and error-code-2, etc., are defined in Appendix B.
5. This clause may be used as many times as necessary to define appropriate procedures for specified error conditions.
6. Not all error codes need be specified. Selected error codes may appear in only one USE statement.
7. The ANY ABORT option may be used only once, and no other option may be used with it.
8. When a trace is made, a plain language statement defining the error and, when possible, the records or chains involved appears on the execution report. (See Appendix B.) All fatal I-D-S error conditions are traced prior to aborting.

The trace prints (1) the name of the subroutine called, (2) the name of the subroutine that called it, and (3) the alter number from which (1) was called. The trace continues to the point at which the main program is the calling routine. An example is shown below:

```
                IDS ERROR
RETRIEVE NEXT IN CHAIN NO CURRENT EXISTS MT0010-DT0020
TRACE OF ABOVE ERROR FOLLOWS -----
QUIT CALLED BY .QFWD   AT ALTER 000149
:QFWD CALLED BY .QCHN  AT ALTER 000131
:QCHN CALLED BY C.LDIN AT ALTER 000054
                TRACE END
```

9. Example:

```
.
.
PROCEDURE DIVISION.
START-PARA.
.
.
ENTER IDS.
USE ERROR-PARA-1 ON D01.
.
.
ERROR-PARA-1.
DISPLAY "DUPLICATE RECORD FOUND".
.
.
ENTER IDS.
USE ABORT-PARA-1 THRU ABORT-END
ON 15,31.
.
.
ABORT-PARA-1.
DISPLAY "RECOVERY REQUIRED - DELETE REPORTS".
.
.
ABORT-END.
CLOSE IN-FILE, OUT-FILE.
```

4. Translator Processing

The I-D-S Translator is a system program which is called from system storage by the \$ IDS control card.

At the time of allocation for the I-D-S Translator, sufficient resources (memory and peripheral devices) are allocated to provide for COBOL. When the Translator has completed its function, it passes control to COBOL using the GECOS entry point GECALL. Figure 16 is a flow diagram of the compilation process of an I-D-S program.

PAGE EJECT AND COMDK LABELING

Page Eject in the Listing

The user can indicate that he desires a page eject in the listing by including a *EJECT card at the appropriate point. A *EJECT (starting in column 7) is treated as comments by the translator and causes a page eject in the listing before the printing of the *EJECT card. The *EJECT is passed to COBOL and causes a subsequent print and page eject in the COBOL portion of the listing.

COMDK Labeling

The translator uses the contents of columns 73-80 of the first source card encountered and includes it in columns 73-80 of any compressed deck created by the translator. Labeling and sequencing conform to the specifications of IOEDIT (see GE-600 Line File and Record Control, CPB-1003).




Figure 16. I-D-S Compilation and Execution Process

\$ IDS CONTROL CARD DESCRIPTION

The \$ IDS control card is used to call the I-D-S Translator. The operand field is used to specify the system options.

Example:

1	8	16
\$	IDS	Options

Options available with I-D-S/COBOL are listed below; standard options are underlined.

- LSTIN - An I-D-S listing and COBOL input listing will be prepared
- NLSTIN - No I-D-S listing of input will be prepared. Option is reset to LSTIN prior to calling COBOL
- LSTOU - A listing of assembled object program output will be prepared by GMAP
- NLSTOU - No listing of output will be prepared
- NDECK - No binary object program deck will be prepared
- DECK - A binary object program deck will be prepared as output by GMAP
- COMDK - A compressed deck of the source program will be prepared during translation
- NCOMDK - No compressed deck of the source program will be prepared
- DUMP - Slave core dump will be produced if activity terminates abnormally
- NDUMP - Only a panel dump of program registers will be produced if activity terminates abnormally
- ON6 - COBOL will generate a REF ON so that GMAP will build a Symbol Reference Table
- COPY - A COBOL copy prepass is required (see rule 4)
- NCOPY - No COBOL copy prepass is required
- SYMTAB - GMAP will prepare a listing of the Symbol Reference Table (if one has been built) even though NLSTOU is also specified

Rules:

1. The \$ IDS control card must precede the source cards of each program or subprogram to be processed and must precede any other control card associated with that activity.
2. The options can be listed in any order in the operand field.
3. If no options are specified in the operand field, GECOS uses the standard options (underlined).
4. All source decks which use the COPY clause or the RENAMING file option (see GE-600 Line COBOL, CPB-1652) must use the COPY option.

SAMPLE OUTPUT PRODUCED BY THE I-D-S TRANSLATOR

PAGE 1
:SDL-12 CHG02

54975 02 09-26-68 10,291 GE600 INTEGRATED STORE TRANSLATOR

IDS ALTER NOS,

```

00001 IDENTIFICATION DIVISION .
00002 PROGRAM-ID, 5IDS .
00003 000030 AUTHOR, VANDERBUR ,
00004 DATE-WRITTEN , .
00005 000050 ENVIRONMENT DIVISION,
00006 000060 CONFIGURATION SECTION,
00007 000070 SOURCE-COMPUTER, GE-635,
00008 000080 OBJECT-COMPUTER, GE-635;
00009 000090 INPUT-OUTPUT SECTION,
00010 000100 FILE-CONTROL.
00011 000110 SELECT IDS TEST-FILE ASSIGN TO TF,
00012 000130 I-O-CONTROL.
00013 000150 DATA DIVISION,
00014 FILE SECTION,
00015 WORKING-STORAGE SECTION .
00016 77 PAGER PICTURE 999999 COMPUTATIONAL-1 ,
00017 77 COUNT PICTURE 9(6) COMPUTATIONAL-1 ,
00018 77 LIMIT-IS PICTURE 999999 COMPUTATIONAL-1 ,
00019 77 CTLR PICTURE 9(6) ,
00020 01 LOOPER ,
00021 05 LIMITER PICTURE 9(6) ,
00022 05 FILLER SIZE 74 .
00023 01 GONOGO .
00024 05 TSTIT PICTURE XXXXXX .
00025 88 UGONN VALUE "GO " ,
00026 05 FILLER SIZE 74 .
00027 000390 IDS SECTION,
00028 01 CCBLOXK .
00029 02 DIRECT-REFERENCE SIZE IS 8 USAGE IS COMPUTATIONAL-1
00030 SYNCHRONIZED RIGHT,
00031 02 FIRST-REFERENCE SIZE IS 8 USAGE IS COMPUTATIONAL-1
00032 SYNCHRONIZED RIGHT,
00033 02 LAST-REFERENCE SIZE IS 8 USAGE IS COMPUTATIONAL-1
00034 SYNCHRONIZED RIGHT,
00035 02 RECORD-TYPE SIZE IS 4 USAGE IS COMPUTATIONAL-1
00036 SYNCHRONIZED RIGHT,
00037 02 REC-FILE SIZE IS 6 CLASS IS ALPHANUMERIC
00038 VALUE IS "C000T",
00039 02 ERROR-REFERENCE SIZE IS 3 CLASS IS ALPHANUMERIC
00040 SYNCHRONIZED RIGHT,
00041 01 TEST-FILE
00042 PAGE CONTAINS 1920 CHARACTERS
00043 FILE CONTAINS 480 PAGES,
00044 01 PRIME-ER TYPE 555 RETRIEVAL VIA PRIME FIELD ,
00045 02 PRIME PICTURE 99999999 .
00046 02 ABCDEF PICTURE 999 .
00047 01 THE-MASTER
00048 TYPE IS 990
00049 RETRIEVAL VIA CALC CHAIN
00050 PAGE-RANGE 121 TO 121

```

54975 02 09-26-68 10.291 GE600 INTEGRATED STORE TRANSLATOR

IDS ALTER NOS;

00038
00039 02 MASTER-FIELD PICTURE 999999 ,
00040 02 MASTER-DATA PICTURE X(12) ,
00041 98 CALC CHAIN DETAIL
00042 RANDOMIZE ON MASTER-FIELD ,
00043 98 THE-CHAIN CHAIN MASTER CHAIN-ORDER
00044 IS SORTED WITHIN TYPE,
00045 98 PAGE-TABLE CHAIN MASTER CHAIN-ORDER IS SORTED .
00046 01 QUAD1
00047 TYPE IS 001
00048 RETRIEVAL VIA CALC CHAIN
00049 .
00050 02 QUAD1-NUM PICTURE 999999 ,
00051 02 QUAD1-FIELD SIZE 24 .
00052 98 CALC CHAIN DETAIL
00053 RANDOMIZE ON QUAD1-NUM ,
00054 98 THE-CHAIN CHAIN DETAIL SELECT CURRENT
00055 ASCENDING KEY IS QUAD1-NUM.
00056 01 QUAD2
00057 TYPE IS 002
00058 RETRIEVAL VIA CALC CHAIN
00059 .
00060 02 QUAD2-NUM PICTURE 999999 ,
00061 02 QUAD2-FIELD SIZE 24 .
00062 98 CALC CHAIN DETAIL
00063 RANDOMIZE ON QUAD2-NUM ,
00064 98 THE-CHAIN CHAIN DETAIL SELECT CURRENT
00065 ASCENDING KEY IS QUAD2-NUM.
00066 01 QUAD3
00067 TYPE IS 003
00068 RETRIEVAL VIA CALC CHAIN
00069 .
00070 02 QUAD3-NUM PICTURE 999999 ,
00071 02 QUAD3-FIELD SIZE 24 .
00072 98 CALC CHAIN DETAIL
00073 RANDOMIZE ON QUAD3-NUM ,
00074 98 THE-CHAIN CHAIN DETAIL SELECT CURRENT
00075 ASCENDING KEY IS QUAD3-NUM.
00076 01 QUAD4
00077 TYPE IS 004
00078 RETRIEVAL VIA CALC CHAIN
00079 .
00080 02 QUAD4-NUM PICTURE 999999 ,
00081 02 QUAD4-FIELD SIZE 24 .
00082 98 CALC CHAIN DETAIL
00083 RANDOMIZE ON QUAD4-NUM ,
00084 98 THE-CHAIN CHAIN DETAIL SELECT CURRENT
00085 ASCENDING KEY IS QUAD4-NUM.
00086 01 PAGE-LIST
00087 TYPE IS 050

DECK SETUPS

The following deck setups show the most common uses of the I-D-S Translator: (1) translate and compile; and (2) translate, compile, and execute.

Translate and Compile

1	8	16
\$	IDENT	
\$	IDS	
	.	Source Program
	.	
\$	ENDJOB	
***EOF		

With the above deck setup, the I-D-S Translator is called, and the source program is translated into a form acceptable to COBOL. COBOL is called to compile the translated program. Since no options are specified in the \$ IDS card, standard I-D-S/COBOL options are used.

Translate, Compile, and Execute

1	8	16
\$	IDENT	
\$	PROGRAM	QUTU
\$	DATA	.Q
	.	
	.	Directives
	.	
\$	"file"	A1,Options
\$	DATA	I*
	.	
	.	Directives
	.	
\$	IDS	Options
	.	
	.	Source program
	.	
\$	EXECUTE	Options
\$	"file"	fc,Options
		fc is the same file code
		specified in the File Code
		Section of the user's program
\$	DATA	.Q
	.	
	.	Directives
	.	
\$	ENDJOB	
***EOF		

The deck setup above assumes a temporary I-D-S data base where "file" can reference any mass storage device such as PRMFL, DISC, MASS, etc.

OBJECT PROGRAM EXECUTION

The I-D-S object program consists of a modular set of subroutines which interpretively execute the I-D-S commands. GELOAD loads these subroutines as a result of the calls generated by the compilation process.

Because of the interpretive mode of execution, the complete data description of the I-D-S data file, also generated by the Translator, must be available to these routines.

Example:

Deck setup for execution using an I-D-S permanent data file.

1	8	16
\$	IDENT	IDS00,DATABASEMGR,
\$	USERID	IDSFOURYQUAD\$DATABASE
\$	OBJECT	
	.	
	.	
	.	
\$	DKEND	
\$	EXECUTE	
\$	LIMITS	
\$	PRMFL	A1,R/W,R,IDSFOURYQUAD/QUAD01
\$	PRMFL	A2,R/W,R,IDSFOURYQUAD/QUAD02
\$	PRMFL	A3,R/W,R,IDSFOURYQUAD/QUAD03
\$	PRMFL	A4,R/W,R,IDSFOURYQUAD/QUAD04
	.	
	.	
	.	

5. I-D-S Data File Structure Descriptions

DEFINITION STRUCTURE

The Definition Structure required by I-D-S is a list structure which reflects the description of the records of the I-D-S data file. It defines the master/detail relationships between records, chain characteristics, and the physical and control characteristics of every field of every record type in the I-D-S data file.

The organization of a Definition Structure using the I-D-S shorthand technique is shown in Figure 17.




Figure 17. I-D-S Definition Structure

The Definition Structure is described in the following sections.

Communication Control Block

The Communication Control Block entry must be supplied as the master of the Record-Type Chain. It serves as the communication area for data which must be passed between the user's program and the I-D-S subroutines. The machine format of the entry is shown in Figure 18.

		Bits						
		0	5	11	17	23	29	35
LOC-CCB		0	0	MBZ	DIRECT-REFERENCE			
	+1	MBZ			FIRST-REFERENCE			
	+2	MBZ			LAST-REFERENCE			
	+3	MBZ			Record Type			
	+4	Record Type Chain Next			MBZ	File Code		
	+5	MBZ			ERROR-REFERENCE			
	+6	MBZ	AUTHORITY		MBZ	OPEN Mode		

Figure 18. Format of Communication Control Block Entry

The bit structure of the format shown in Figure 18 serves the following purposes:

- LOC-CCB Symbolic location of Communication Control Block.
- 0-5 Definition Type--an octal code of 00.
 - 6-11 Must be zero.
 - 12-35 DIRECT-REFERENCE--a reference code of the record last processed by any STORE or RETRIEVE.
- LOC-CCB+1
- 0-11 Must be zero.
 - 12-35 FIRST-REFERENCE--reference code of the first record to be retrieved by the RETRIEVE EACH verb. The value is supplied by the user's program. After each retrieval, the I-D-S subroutines modify the value to the next reference code.

LOC-CCB+2

- 0-11 Must be zero.
- 12-35 LAST-REFERENCE--a value supplied by the user's program. When this reference code is reached, the RETRIEVE EACH verb will execute the AT END procedure.

LOC-CCB+3

- 0-11 Must be zero.
- 12-35 Record type of the last record processed by any STORE or RETRIEVE. The value is supplied by an I-D-S subroutine.

LOC-CCB+4

- 0-17 Record Type Chain Next--the assigned symbol of the first Record Definition Structure.
- 18-23 Must be zero.
- 24-35 File Code--the user-supplied, two-character file code assigned to the I-D-S data file.

LOC-CCB+5

- 0-17 Must be zero.
- 18-35 ERROR-REFERENCE--a BCD code for an error condition encountered during execution. If there is no error, the value supplied by I-D-S will be zero.

LOC-CCB+6

- 0-5 Must be zero.
- 6-17 AUTHORITY--a value supplied by the user.
- 18-29 Must be zero.
- 30-35 OPEN Mode--a processing mode supplied via the OPEN routine.

Record Definition Entry

A Record Definition entry must be supplied for each data record type in the I-D-S data file. In addition, one such entry must be supplied for the Page Header record. The Record Definition entry is the master of the Master Chain, Detail Chain, and the Field Chain; it is a detail of the Record-Type Chain. The format is shown in Figure 19.

	0	5	8	11	17	29	35			
LOC-SYM	0	1	MBZ	Record Type		Record Size	MBZ	S	P	R
+1	Page Interval					Master Chain Next				
+2	Field Chain Next					Detail Chain Next				
+3	Authority			Current Record Reference Code						
+4	Record Type Chain Next					MBZ				
+5	Minimum Page Range					Maximum Page Range				

Figure 19. Format of Record Definition Entry

The bit structure of the format shown in Figure 19 serves the following purposes:

- LOC-SYM Symbol equivalent to the record name.
- 0-5 Definition Type--an octal code of 01.
- 6-7 Must be zero.
- 8-17 Record Type--a number from 1 to 999 assigned to each data record; 1000(10) is assigned to the Page Header record; for a Page Header record, the number is 1003(10).
- 18-29 Record Size--number of characters in the record including all control and chain fields.
- 30-32 Must be zero.
- 33 S--Storage Classification Indicator
- 0--Record is stored relative to the chain defined as the Retrieval Chain for this record.
- 1--Record is stored relative to the chain defined as the Storage Chain, which is not the same as the Retrieval Chain.
- 34 P--Page Range Indicator
- 0--Absolute Page Range not specified for this record type (see LOC-SYM+5).
- 1--Absolute Page Range is specified (see LOC-SYM+5).
- 35 R--Retrieval Classification Indicator
- 0--Secondary or calculated record
- 1--Primary record

LOC-SYM+1

- 0-17 Page Interval--Number of pages to be skipped relative to the page in which the last record of this type was stored. This only applies to primary or secondary records.
- 18-35 Master Chain Next--the assigned symbol of the first Master Definition for this record. If this record is not the master of any chain, this is the assigned symbol of the Record Definition.

LOC-SYM+2

- 0-17 Field Chain Next--assigned symbol of the first Field Definition for this record. If there are no data fields, then this is the assigned symbol of the Record Definition.
- 18-35 Detail Chain Next--assigned symbol of the first Detail Definition for this record. If this record is not the detail in any chain, then this is the assigned symbol of the Record Definition.

LOC-SYM+3

- 0-11 AUTHORITY--A value supplied by the user not to exceed 4095(10) which serves as a lock for the data contained in the record. Reference to this record during program execution is allowed only when a matching key is specified by the .QOPEN calling sequence.
- 12-35 Current Record Reference Code--reference code of the last record stored or retrieved of this record type. This is supplied by I-D-S during execution.

LOC-SYM+4

- 0-17 Record Type Chain Next--assigned symbol of the next Record Definition of the Definition Structure. If this is the last Record Definition entry, this field contains the symbolic location of the Communication Control Block.
- 18-35 Must be zero.

LOC-SYM+5

(For P, see LOC-SYM, bit 34.)

If P = 1, then:

- 0-17 Minimum Page Range--the first page number of a range of pages into which all records of this type are to be stored.
- 18-35 Maximum Page Range--the last page number of a range of pages into which all records of this type are to be stored.

If P = 0 and LOC-SYM+5, bits 0-35 = 0, then:

No Page Range is specified for this record type.

If P = 0 and LOC-SYM+5, bits 0-35 ≠ 0, then:

- 0-17 Minimum Page Range Pointer--points to a word in which bit positions 18-35 contain the first page number of a range of pages into which all records of this type are to be stored.
- 18-35 Maximum Page Range Pointer--points to a word in which bit positions 18-35 contain the last page number of a range of pages into which all records of this type are to be stored.

Detail Definition

A Detail Definition entry must be supplied each time a record is a detail in some chain. If a record is a detail in three different chains, three Detail Definition entries must be supplied. The Detail Definition entry is a detail of the Chain Chain and of the Detail Chain. It is also the master of the Control Chain. The machine format of this entry is shown in Figure 20.




Figure 20. Machine Format for Detail Definition Entry

The areas in the format shown in Figure 20 serve the following purposes:

- LOC-SYM Symbol assigned to this entry.
- 0-5 Definition Type--an octal code of 04.
- 6-7 Must be zero.
- 8-17 Data Record Type--same as that specified by the Record Definition entry for this record.
- 18-25 Must be zero.
- 26-29 Order--a code to represent the chain-order of the various details of this chain. Note that when several different record types are defined as details of the same chain, the chain-order must be the same for all records. The chain-order for a CALC chain must be 11(8) for after current.

<u>Octal Code</u>	<u>Chain-order</u>
06	Sorted Within Type
04	Sorted
10	First in Chain
00	Last in Chain
01	Before Current
11	After Current

- 30-31 DUP--Duplicate Records Indicator
- 00--Not allowed
- 01--Allowed First
- 11--Allowed Last
- 32 C--CALC Chain Detail Indicator
- 0--Not a CALC Chain
- 1--CALC Chain
- 33 U--Chain Master Indicator
- 0--The master of this chain is a unique master retrievable via the MATCH-KEY fields defined for this chain.
- 1--The master of this chain is the current master record of its type.
- 34 S--Storage Chain Indicator
- 0--Record is not stored relative to this chain.
- 1--Record is stored relative to its logical position in this chain.
- 35 R--Retrieval Chain Indicator
- 0--Associative retrieval of this record not possible via this chain.
- 1--Associative retrieval of this record must be via this chain.

LOC-SYM+1

- 0-17 Chain Chain Next--assigned symbol of the next Detail Definition of this chain if there is more than one detail record type in the chain. If there is only one Detail Definition or if this is the last of several, then this is the assigned symbol of the Master Definition for this chain.
- 18-35 Control Chain Next--assigned symbol of the first Control Definition for this chain or, if none, the symbol assigned to this Detail Definition.

LOC-SYM+2

- 0-17 Chain Chain Head--assigned symbol of the Master Definition of this chain.
- 18-35 Detail Chain Next--assigned symbol of the next Detail Definition for this record if the record is a detail in more than one chain. If there is only one Detail Definition or if this is the last of several, then this is the assigned symbol of the Record Definition for this record.

LOC-SYM+3

- 0-11 Next Position--the character position, relative to the first character of the record, in which the first character of the chain next pointer is found.
- If this is a CALC chain detail, the NEXT chain field must be the first field following the Record Size Field of the record; that is, it must be defined as beginning in character position 5.
- 12-17 Must be zero.
- 18-35 Detail Chain Head--assigned symbol of the Record Definition for this record.

LOC-SYM+4

- 0-11 Prior Position--the character position, relative to the first character of the record, in which the first character of the chain prior pointer is found. If the chain is not prior processable, this value is zero.
- When a detail record of a given chain contains a prior pointer, all records of the chain must contain a prior pointer.
- 12-23 Head Position--the character position, relative to the first character of the record, in which the first character of the chain head pointer is found. If the chain is not a headed chain, this character is zero.
- 24-35 Must be zero.

Master Definition

A Master Definition entry must be supplied each time a record is defined as the master of some chain. The Master Definition is a detail of the Master Chain and the master of the Chain Chain. The machine format of this entry is shown in Figure 21.

Bits	0	5	7	11	17	35
LOC-SYM	0	2	MBZ	Data Record Type		Master Chain Head
+1	Chain Chain Next				Master Chain Next	
+2	MBZ			Reference Code of Chain Master		
+3	Next Position			Reference Code of Chain Prior		
+4	Prior Position			Reference Code of Chain Current		
+5	MBZ			Reference Code of Chain Next		
+6	MBZ			Reference Code of Key Record		

Figure 21. Machine Format for Master Definition Entry

The areas in the format shown in Figure 21 serve the following purposes:

- LOC-SYM Symbol equivalent to chain name.
- 0-5 Definition Type--an octal code of 02
- 6-7 Must be zero.
- 8-17 Data Record Type--same as that specified for the Record Definition entry for this record.
- 18-35 Master Chain Head--assigned symbol of the Record Definition entry for this record.
- LOC-SYM+1
- 0-17 Chain Chain Next--assigned symbol of the first Detail Definition for this chain. If the chain has no detail records defined, then this is the symbol of this Master Definition.
- 18-35 Master Chain Next--assigned symbol of the next Master Definition if this record is the master of more than one chain. If the record is the master of only one chain or the master of the last of several chains, then this coding is the symbol of the Record Definition for this record.

LOC-SYM+2

- 0-11 Must be zero.
- 12-35 Reference Code of Chain Master--reference code of the Master Record of the chain defined by this Master Definition. This value is supplied by I-D-S during execution.

LOC-SYM+3

- 0-11 Next Position--the character position, relative to the first character of the record, in which the first character of the chain next pointer is found.
- 12-35 Reference Code of Chain Prior--reference code of the prior record of the chain defined by this Master Definition. This is supplied by I-D-S during execution.

LOC-SYM+4

- 0-11 Prior Position--the character position, relative to the first character of the record, in which the first character of the chain prior pointer is found. If the master record is not prior processable, this value is zero.
- 12-35 Reference Code of Chain Current--reference code of the current record of the chain defined by this Master Definition. This value is supplied by I-D-S during execution.

LOC-SYM+5

- 0-11 Must be zero.
- 12-35 Reference Code of Chain Next--reference code of the next record of the chain defined by this Master Definition. This is supplied by I-D-S during execution.

LOC-SYM+6

- 0-11 Must be zero.
- 12-35 Reference Code of Key Record--reference code of the record to which a record will be relinked if there is an error in modification. This code is supplied by I-D-S during execution.

Field Definition

A Field Definition entry must be supplied for each data field contained in the record. (Note that Field Definitions are not supplied for the In addition, if the record is defined as a secondary record, a Field Definition must be supplied for all MATCH-KEY fields defined. If the record is defined as a primary record, a Field Definition must be supplied for the field which is equivalent to the reference code. The Field Definition entry is a detail in the Field Chain and is the master of the Modify Chain. The machine format of the entry is shown in Figure 22.

	0	5	17	24	33	35		
LOC-SYM	1	0	MBZ	C	AF	U	MBZ	Field Increment
+1	Location of Working Storage			Field Size		MBZ	First Char.	
+2	Field Chain Next			Modify Chain Next				

Figure 22. Machine Format for Field Definition Entry

The areas in the format shown in Figure 22 serve the following purposes:

- LOC-SYM Symbol assigned to this entry.
- 0-5 Definition Type--an octal code of 10.
- 6-17 Must be zero.
- 18 C--Computational Mode Indicator (*)
- 0--Noncomputational field recorded in BCD.
 1--Computational field recorded in binary. (The implied size is 6 or 12 characters.)
- 19-20 AF--Arithmetic Form (*)
- If bit 18=1 then:
- 00--Single Precision, Fixed Point
 01--Single Precision, Floating Point
 10--Double Precision, Fixed Point
 11--Double Precision, Floating Point,

If bit 18=0 then:

00--Alphanumeric
01--Alphabetic
10--Numeric
11--Signed numeric (sign indicated by zone bits of
low-order character of the field).

21 U--Unique Field Indicator

0--Field is not a unique or control field
1--Field is unique and required for identification
of the record

When this record is a primary record its unique field is, by definition, the reference code. Since a Field Definition entry is not supplied for the reference code, a separate entry must be supplied to define the working-storage location for the field which is equivalent to the reference code. This entry must not include the Field Definition specifications indicated in this section by (*), since the field is not actually contained in the data record. I-D-S assumes that the format of this field in working storage is eight characters, BCD numeric.

22-23 Must be zero.

24-35 Field Increment (*)--character position of the first character of a field; increment zero is the first character of the record.

LOC-SYM+1

0-17 Location of Working Storage--assigned symbol of the leftmost word of working storage defined for this field. The symbol is equivalent to the field name.

18-29 Field Size--the number of characters in the field as it exists in the record or in working storage.

30-32 Must be zero.

33-35 First Character--position of the first character of the field within the first word of working storage.

LOC-SYM+2

0-17 Field Chain Next--assigned symbol of the next Field Definition of this record, if there is more than one field in the record. If there is only one field or if this is the last of several, then this value is the assigned symbol of the Record Definition for the record.

18-35 Modify Chain Next--assigned symbol of the first Control Definition for this field or, if the field is not a control field, the symbol of this Field Definition.

Control Definition

A Control Definition entry must be supplied each time a field is defined as a control field of some chain. A control field is defined as a sort field, MATCH-KEY field, or a RANDOMIZE field. The Control Definition entry is a detail of the Modify Chain and of the Control Chain. The machine format of this entry is shown in Figure 23.

	0	5	14	17	35	
LOC-SYM	2	0	MBZ	R	CNTL	Control Chain Head
+1	Location of MATCH-KEY Field Definition				Control Chain Next	
+2	Modify Chain Head			Modify Chain Next		

Figure 23. Machine Format for Control Definition Entry

The areas in the format shown in Figure 23 serve the following purposes:

LOC-SYM Symbol assigned to this entry.

0-5 Definition Type--an octal code of 20

6-13 Must be zero.

14 R--Match Control Indicator

0--Equal match required
1--Match equal or greater (Range Record)

15-17 CNTL--Control field type

001--RANDOMIZE control field
010--Sort Control ascending sequence
011--Sort Control descending sequence
100--MATCH-KEY control field

18-35 Control Chain Head--assigned symbol of the Detail Definition of the chain controlled by this Control Definition.

LOC-SYM+1

0-17 Location of MATCH-KEY Field Definition--assigned symbol of the MATCH-KEY Field Definition associated with this SYNONYM Field. If there is no SYNONYM, this symbol is zero.

18-35 Control Chain Next--assigned symbol of the next Control Definition for the chain. If this is the last or only Control Definition, then the code is the symbol of the Detail Definition.

When several sort control fields are defined for a given chain, they must occur in sequence from major sort control to minor sort control.

LOC-SYM+2

0-17 Modify Chain Head--assigned symbol of the Field Definition for this control field.

18-35 Modify Chain Next--assigned symbol of the next Control Definition if this field is a control field in some other chain. If this is the last or only Control Definition for this field, then the code is the symbol of the Field Definition.

A definition structure produced by the I-D-S Translator and a definition structure as expanded by GMAP appear on the following pages.

IDS ALTER NCS,

SAMPLE OUTPUT

	ETC	CALC
RD2435	,OFD	0,0,000015,0024,FC5697,RD2434,
	ETC	RD2435,RD5697,
	ETC	QUAD3-FIELD
RD2434	,OFD	0,0,000009,0006,FC5953,RD2433,
	ETC	RD2437,RD5953,
	ETC	QUAD3-NUM
RD2437	,OCD	0,1,RD2436,RD2436,RD2434,RD2434,
	ETC	0
RD7233	,ORD	002,000043,0,0,0,000000,
	ETC	RD7233,RD7238,RD7235,0000,RD4737,
	ETC	000000,000000,QUAD2
RD7238	,ODD	002,10,0,0,1,0,
	ETC	0,RD7236,RD7233,RD4742,RD4097,RD7238,
	ETC	0039,0000,0000,
	ETC	THE-CHAIN
RD7236	,ODD	002,11,0,1,0,1,
	ETC	1,RD7233,RD7233,RD4740,RD8129,RD7237,
	ETC	0005,0000,0000,
	ETC	CALC
RD7235	,OFD	0,0,000015,0024,FC4353,RD7234,
	ETC	RD7235,RD4353,
	ETC	QUAD2-FIELD
RD7234	,OFD	0,0,000009,0006,FC1025,RD7233,
	ETC	RD7237,RD1025,
	ETC	QUAD2-NUM
RD7237	,OCD	0,1,RD7236,RD7236,RD7234,RD7234,
	ETC	0
RD4737	,ORD	001,000043,0,0,0,000000,
	ETC	RD4737,RD4742,RD4739,0000,RD4481,
	ETC	000000,000000,QUAD1
RD4742	,ODD	001,10,0,0,1,0,
	ETC	0,RD4740,RD4737,RD4097,RD4097,RD4742,
	ETC	0039,0000,0000,
	ETC	THE-CHAIN
RD4740	,ODD	001,11,0,1,0,1,
	ETC	1,RD4737,RD4737,RD4484,RD8129,RD4741,
	ETC	0005,0000,0000,
	ETC	CALC
RD4739	,OFD	0,0,000015,0024,FC1537,RD4738,
	ETC	RD4739,RD1537,
	ETC	QUAD1-FIELD
RD4738	,OFD	0,0,000009,0006,FC8065,RD4737,
	ETC	RD4741,RD8065,
	ETC	QUAD1-NUM
RD4741	,OCD	0,1,RD4740,RD4740,RD4738,RD4738,
	ETC	0
RD4481	,ORD	990,000035,0,1,0,000000,
	ETC	RD7809,RD4484,RD4483,0000,RD0513,
	ETC	000121,000121,THE-MASTER

IDS ALTER NCS,

RC7809	,QMD	990, RD4097, RD4481, RD0196, 0031, 0000,
	ETC	PAGE=TABLE
RC4097	,QMD	990, RD4481, RD4481, RD5062, 0027, 0000,
	ETC	THE=CHAIN
RC4484	,QDD	990, 11, 0, 1, 0, 1,
	ETC	1, RD4481, RD4481, RD8129, RD8129, RD4485,
	ETC	0005, 0000, 0000,
	ETC	CALC
RC4483	,QFD	0, 0, 000015, 0012, FC0321, RD4482,
	ETC	RD4483, RD0321,
	ETC	MASTER-DATA
RC4482	,QFD	0, 0, 000009, 0006, FC1089, RD4481,
	ETC	RD4482, RD1089,
	ETC	MASTER-FIELD
RC4485	,QCD	0, 1, RD4484, RD4484, RD4482, RD4482,
	ETC	U
RC0513	,ORD	1000, 000022, 0, 0, 1, 000000,
	ETC	RD8129, RD0513, RD0513, 0000, CCBLOC,
	ETC	000000, 000000, XPAGE=HEADXX
RC8129	,QMD	1000, RD0513, RD0513, RD5060, 0005, 0000,
	ETC	CALC
	USE	
	TRA	1, IDS,
LS9000	ZERO	000000, 000002
EE0001	VFD	2670, 10/990
DE0001	ZERO	0, 03
	,,IDS, NULL	
	ENTER	COBOL,
	ENTER DEFINITIONS	,
	SYMBOL RD3137	EQUALS
	LINE=NO	
	SYMBOL FC3137	EQUALS INITIAL CHARACTER OF
	LINE=NO	
	IDS SIZE	000002 EQUALS
	LINE=NO	
	SYMBOL RD1473	EQUALS
	PAGE=NO	
	SYMBOL FC1473	EQUALS INITIAL CHARACTER OF
	PAGE=NO	
	IDS SIZE	000006 EQUALS
	PAGE=NO	
	SYMBOL RD1217	EQUALS
	QUAD4-FIELD	
	SYMBOL FC1217	EQUALS INITIAL CHARACTER OF
	QUAD4-FIELD	
	IDS SIZE	000024 EQUALS
	QUAD4-FIELD	
	SYMBOL RC7873	EQUALS
	QUAD4=NUM	
	SYMBOL FC7873	EQUALS INITIAL CHARACTER OF

42447 09 08-06-69 17,499

5IDS

000216	004240	004170	033	ZERO	RD8129 CHN CHN NXT, RD4485 CON NXT, RD8129, RD4481 RD8129 CHN CHN HD, RD4481 DET NXT,	
END OF BINARY CARD 5IDS0032						
000217	000500	0004170	003	VFD	12/0005,6/0,18/RD4481 0005 POS NXT, RD4481 DET CHN HD	
000220	000000000000	000	000	VFD	12/0000,12/0000,12/0 0000 PRIOR, 0000 HEAD DETAIL OF CALC CHAIN	
	000221		522	RD4483	QFD	0,0,000015,0012,FC0321,RD4482, RD4483,RD0321, MASTER-DATA
	000221		523		ETC	
	000221		524		ETC	
000221	100000000017	000	000	VFD	06/10,12/0,3/0,1/0,2/0,12/000015 0 CAF, 0 U, 000015 FLD INCR,	
000222	000750001400	010	010	VFD	18/RD0321,12/0012,3/0,3/FC0321 RD0321 WS, 0012 FLD SZ, FC0321 FST CH, RD4482,RD4483	
000223	004224	004221	033	ZERO	RD4482 FLD CHN NXT, RD4483 MOD CHN NXT MASTER-DATA ****FIELD-NAME**** 0,0,000009,0006,FC1089,RD4481, RD4485,RD1089, MASTER-FIELD	
	000224		525	RD4482	QFD	06/10,12/0,3/0,1/0,2/0,12/000009 0 CAF, 0 U, 000009 FLD INCR, 18/RD1089,12/0006,3/0,3/FC1089 RD1089 WS, 0006 FLD SZ, FC1089 FST CH, RD4481,RD4485
	000224		526		ETC	
	000224		527		ETC	
000224	100000000011	000	000	VFD	06/10,12/0,3/0,1/0,2/0,12/000009 0 CAF, 0 U, 000009 FLD INCR, 18/RD1089,12/0006,3/0,3/FC1089 RD1089 WS, 0006 FLD SZ, FC1089 FST CH, RD4481,RD4485	
000225	000754000600	010	010	VFD	06/10,12/0,3/0,1/0,2/0,12/000009 0 CAF, 0 U, 000009 FLD INCR, 18/RD1089,12/0006,3/0,3/FC1089 RD1089 WS, 0006 FLD SZ, FC1089 FST CH, RD4481,RD4485	
000226	004170	004227	033	ZERO	RD4481 FLD CHN NXT, RD4485 MOD CHN NXT MASTER-FIELD ****FIELD-NAME**** 0,1,RD4484,RD4484,RD4482,RD4482, 0	
	000227		528	RD4485	QCD	05/20,8/0,1/0,3/1,18/RD4484 0 R, 1 CNTL, RD4484 CON CHN HD, 0, RD4484
	000227		529		ETC	
000227	200001004214	003	003	VFD	0 LOC SYN W.S., RD4484 CON, CHAIN NEXT RD4482,RD4482 RD4482 MOD CH HEAD, RD4482 MOD CHN NXT 1000,000022,0,0,1,000000, RD8129,RD0513,RD0513,0000,CCBLOC, 000000,000000,XPAGE=HEADXX 06/1,2/0,10/1000,12/000022,3/0, 1/0,1/0,1/1 1000 RECORD TYPE, 000022 REC SIZE, 0 S, 0 P, 1 R,	
000230	000000	004214	003	ZERO	0, RD4484	
000231	004224	004224	033	ZERO	0 LOC SYN W.S., RD4484 CON, CHAIN NEXT RD4482,RD4482 RD4482 MOD CH HEAD, RD4482 MOD CHN NXT 1000,000022,0,0,1,000000, RD8129,RD0513,RD0513,0000,CCBLOC, 000000,000000,XPAGE=HEADXX 06/1,2/0,10/1000,12/000022,3/0, 1/0,1/0,1/1 1000 RECORD TYPE, 000022 REC SIZE, 0 S, 0 P, 1 R,	
	000232		530	RD0513	QCD	0 LOC SYN W.S., RD4484 CON, CHAIN NEXT RD4482,RD4482 RD4482 MOD CH HEAD, RD4482 MOD CHN NXT 1000,000022,0,0,1,000000, RD8129,RD0513,RD0513,0000,CCBLOC, 000000,000000,XPAGE=HEADXX 06/1,2/0,10/1000,12/000022,3/0, 1/0,1/0,1/1 1000 RECORD TYPE, 000022 REC SIZE, 0 S, 0 P, 1 R,
	000232		531		ETC	
	000232		532		ETC	
000232	011750002601	000	000	VFD	0 LOC SYN W.S., RD4484 CON, CHAIN NEXT RD4482,RD4482 RD4482 MOD CH HEAD, RD4482 MOD CHN NXT 1000,000022,0,0,1,000000, RD8129,RD0513,RD0513,0000,CCBLOC, 000000,000000,XPAGE=HEADXX 06/1,2/0,10/1000,12/000022,3/0, 1/0,1/0,1/1 1000 RECORD TYPE, 000022 REC SIZE, 0 S, 0 P, 1 R,	
000233	000000	004240	003	ZERO	000000, RD8129 000000 PG INT, RD8129 MST CHN NEXT, RD0513, RD0513 RD0513 FLD CHN NXT, RD0513 DET CHN NXT, 12/0000, 24/0 0000 AUTHORITY, CCBLOC, 0 CCBLOC REC TYPE CHN NXT	
000234	004232	004232	033	ZERO	000000, RD8129 000000 PG INT, RD8129 MST CHN NEXT, RD0513, RD0513 RD0513 FLD CHN NXT, RD0513 DET CHN NXT, 12/0000, 24/0 0000 AUTHORITY, CCBLOC, 0 CCBLOC REC TYPE CHN NXT	
000235	000000000000	000	000	VFD	000000, RD8129 000000 PG INT, RD8129 MST CHN NEXT, RD0513, RD0513 RD0513 FLD CHN NXT, RD0513 DET CHN NXT, 12/0000, 24/0 0000 AUTHORITY, CCBLOC, 0 CCBLOC REC TYPE CHN NXT	
000236	000744	000000	010	ZERO	000000, RD8129 000000 PG INT, RD8129 MST CHN NEXT, RD0513, RD0513 RD0513 FLD CHN NXT, RD0513 DET CHN NXT, 12/0000, 24/0 0000 AUTHORITY, CCBLOC, 0 CCBLOC REC TYPE CHN NXT	

```

42447 09 08-06-69 17.499 5IDS
000237 000000 000000 000 ZERO 000000,000000
000240 021750004232 000 533 RD0129 .QAD 000000 PAGE R MIN, 000000 PAGE R MAX
000241 004037 004232 033 534 ETC 1000, RD0513, RD0513, RD0600, 0005, 0000,
VFD CALC
VFD 06/2, 2/0, 10/1000, 18/RD0513
VFD 1000 REC TYPE% RD0513 MST CHN RD,
RD05060, RD0513
RD05060 CHN CHN NXT, RD0513 MST CHN NXT,
VFD 12/0, 24/0
VFD 12/0005, 24/0
VFD 0005 POS NEXT,
VFD 12/0000, 24/0
VFD 0000 POS PRIOR
VFD 2
VFD MASTER OF CALC CHAIN
000610 000614 7100 00 010 535 USE
000611 000000 000002 000 536 TRA ..IDS.
000612 00000001736 000 537 LS9000 ZERO 000000, 000002
000613 000000 000003 000 538 000001 VFD 26/0, 10/990
000614 000000 7010 00 030 539 000001 ZERO 0, 03
540 ..IDS. NULL
541 * ENTER DEFINITIONS
542 000002 TSX1 .CHFFT
543 EDITP ON
000238
000238

```

.QRD - RECORD DEFINITION

(See Figure 19. Format of Record Definition Entry.)

Line	Item
1	① RECORD TYPE
1	② RECORD SIZE
1	③ S - STORAGE CLASSIFICATION INDICATOR
1	④ P - PAGE RANGE INDICATOR
1	⑤ R - RETRIEVAL CLASSIFICATION INDICATOR
1	⑥ PAGE INTERVAL
2	⑦ MASTER CHAIN NEXT
2	⑧ DETAIL CHAIN NEXT
2	⑨ FIELD CHAIN NEXT
2	⑩ AUTHORITY
2	⑪ RECORD TYPE NEXT
3	⑫ MINIMUM PAGE RANGE
3	⑬ MAXIMUM PAGE RANGE
3	⑭ RECORD NAME

FORMAT

```

RDxxxx .QRD ① xxx,xxxxxx,② x,③ x,④ x,⑤ xxxxxx,⑥ Line 1
          ⑦
          ETC RDxxxx,⑧ RDxxxx,⑨ RDxxxx,⑩ xxxxx,⑪ RDxxxx, Line 2
          ⑫
          ETC xxxxxx,⑬ xxxxxx,⑭ x(30) Line 3

```

TRANSLATOR OUTPUT (see preceding Definition Structure sample)

```

RD7233 .QRD 002,000043,0,0,0,000000,
          ETC RD7233,RD7238,RD7235,0000,RD4737
          ETC 000000,000000,QUAD2

```

.QDD - DETAIL DEFINITION

(See Figure 20. Machine Format for Detail Definition Entry.)

Line	Item
1	① RECORD TYPE
1	② CHAIN ORDER
1	③ DUPLICATE RECORD INDICATOR
1	④ CALC CHAIN DETAIL INDICATOR
1	⑤ U - CHAIN MASTER INDICATOR
1	⑥ S - STORAGE CHAIN INDICATOR
2	⑦ R - RETRIEVAL CHAIN INDICATOR
2	⑧ DETAIL CHAIN NEXT
2	⑨ DETAIL CHAIN HEAD
2	⑩ CHAIN CHAIN NEXT
2	⑪ CHAIN CHAIN HEAD
2	⑫ CONTROL CHAIN NEXT
3	⑬ NEXT POSITION
3	⑭ PRIOR POSITION
3	⑮ HEAD POSITION
4	⑯ CHAIN NAME SPECIFIED BY 98 LEVEL

FORMAT

```

RDxxxxx  .QDD  ① ②③④⑤⑥
                xxx,xx,x,x,x,x,
                Line 1

ETC        ⑦ ⑧ ⑨ ⑩ ⑪ ⑫
                x,RDxxxxx,RDxxxxx,RDxxxxx,RDxxxxx,RDxxxxx,
                Line 2

ETC        ⑬ ⑭ ⑮
                xxxx,xxxx,xxxx,
                Line 3

ETC        ⑯
                x(30)
                Line 4
    
```

TRANSLATOR OUTPUT (see preceding Definition Structure sample)

```

RD7238  .QDD  022,10,0,0,1,0
ETC     0,RD7236,RD7233,RD4742,RD4097,RD7238,
ETC     0039,0000,0000,
ETC     THE-CHAIN
    
```

.QMD - MASTER DEFINITION

(See Figure 21. Machine Format for Master Definition Entry.)

Line	Item
1	① RECORD TYPE
1	② MASTER CHAIN NEXT
1	③ MASTER CHAIN HEAD
1	④ CHAIN CHAIN NEXT
1	⑤ NEXT POSITION
1	⑥ PRIOR POSITION
2	⑦ CHAIN NAME SPECIFIED BY 98 LEVEL

FORMAT

```

RDxxxx  .QMD  ①xxx, ②RDxxxx, ③RDxxxx, ④RDxxxx, ⑤xxxx, ⑥xxxx, Line 1
          ETC  ⑦x(30)                                     Line 2
    
```

TRANSLATOR OUTPUT (see preceding Definition Structure sample)

```

RD7809  .QMD  990,RD4097,RD4481,RD0196,0031,0000,
          ETC  PAGE-TABLE
    
```

.QFD - FIELD DEFINITION

(See Figure 22. Machine Format for Field Definition Entry.)

Line	Item
1	① COMPUTATION MODE AND ARITHMETIC FORM 0 = ALPHANUMERIC BCD FIELD 1 = ALPHABETIC BCD FIELD 2 = NUMERIC BCD FIELD 3 = SIGNED NUMERIC BCD FIELD 4 = SINGLE PRECISION FIXED POINT BINARY FIELD 5 = SINGLE PRECISION FLOATING POINT BINARY FIELD 6 = DOUBLE PRECISION FIXED POINT BINARY FIELD 7 = DOUBLE PRECISION FLOATING POINT BINARY FIELD
1	② U - UNIQUE FIELD INDICATOR
1	③ FIELD INCREMENT
1	④ FIELD SIZE
1	⑤ FIRST CHARACTER
1	⑥ FIELD CHAIN NEXT
2	⑦ MODIFY CHAIN NEXT
2	⑧ LOCATION OF WORKING STORAGE
3	⑨ FIELD NAME

FORMAT

```

RDxxxx  .QFD  ①② ③ ④ ⑤ ⑥                Line 1
           x,x,xxxxxx,xxxx,FCxxxx,RDxxxx,
           ⑦ ⑧
ETC      RDxxxx,RDxxxx,                Line 2
           ⑨
ETC      x(30)
    
```

TRANSLATOR OUTPUT (see preceding Definition Structure sample)

```

RD2345  .QFD  0,0,000015,0024,FC5697,RD2434
ETC     RD2435,RD5697,
ETC     QUAD3-FIELD
    
```

.QCD - CONTROL DEFINITION

(See Figure 23. Machine Format for Control Definition Entry.)

Line	Item
1	① R-MATCH CONTROL INDICATOR
1	② CNTL - CONTROL FIELD TYPE
1	③ CONTROL CHAIN HEAD
1	④ CONTROL CHAIN NEXT
1	⑤ MODIFY CHAIN HEAD
1	⑥ MODIFY CHAIN NEXT
2	⑦ LOCATION OF MATCH-KEY FIELD DEFINITION

FORMAT

```

RDxxxx  .QCD  ①② ③ ④ ⑤ ⑥      Line 1
            x,x, RDxxxx, RDxxxx, RDxxxx, RDxxxx,
            ⑦
            ETC  RDxxxx      Line 2
    
```

TRANSLATOR OUTPUT (see preceding Definition Structure sample)

```

RD2437  .QCD  0,1, RD2438, RD2436, RD2434, RD2434,
            ETC  0
    
```

6. Operational Characteristics

I-D-S provides the following capabilities:

A controlled, concurrent access to a common I-D-S structured data file which is created by the File System Activity;

A common journal file for the automatic collection of journal records from each of multiple I-D-S activities in execution;

An integrated set of utility routines to enable recovery and/or restart following a condition which requires restoration of the data file.

Concurrent access to a common I-D-S data file is provided through the concept of subfile definition and allocation. A subfile is defined as a set of pages that fall within the total I-D-S data file. This range may be either the complete I-D-S data file or a portion. The File System Activity (\$ FILSYS) procedures allow the creation, modification, and deletion of subfiles within an I-D-S file.

At execution time, the I-D-S user specifies the subfiles which must be allocated to his activity. Each subfile requested is given an associated access mode.

I-D-S DATA FILE INITIALIZATION

Prior to the operation of any I-D-S program, the mass storage device must have been initialized with a Page Header record as the first record of each page in the I-D-S data file.

The I-D-S utility program QUTI accomplishes this I-D-S data file initialization.

CREATING AN I-D-S DATA FILE

An I-D-S data file may be created on one or many mass storage devices with different hardware characteristics. It can be permanent, temporary, or a combination of the two. In creating this file, the number and location of pages must be considered.

The various directives necessary for creating an I-D-S data file are described below. Only the I-D-S options are included. Refer to the GE-600 Line GECOS III File System Reference Manual, CPB-1513, for a detailed description of the GECOS III File System.

Creating a Permanent I-D-S Data File

A permanent I-D-S data file is created by using the file system FCREAT/IDS/ directive. The options used with FCREAT/IDS/ are:

BASESIZE/n/ Base size is required; /n/ defines the maximum size of the complete I-D-S data file; /n/ must be greater than or equal to 1 and less than or equal to 262143. If multiple files are created to form the complete I-D-S data file, the value of /n/ must be identical on all directives.

RNG/r1,r2/ The page-range is required to define the pages contained in the file; r1 and r2 are the beginning and ending page numbers respectively; r1 must be less than or equal to r2; the values of r1 and r2 must be greater than or equal to 1 and less than or equal to 262143. This range may be either the complete I-D-S data file or a portion.

PAGESIZE/n/ The page size is optional. If it is omitted, a size of 320-words is assumed. When it is present, /n/ must be greater than or equal to 40 and less than or equal to 640. This allows a different page size in each subfile within the complete I-D-S data file.

When /n/ is present, the actual page size used will be adjusted, if necessary, to reflect a multiple of sector size of the hardware device for this file. (For a DSU200 Magnetic Disc Subsystem, page size will be 40×2^n , where n is an integer and $1 \leq n \leq 4$. For a DSU270 or a DSU167 or for an MDS200 Magnetic Drum Subsystem, page size will be $64 \times n$, where n is an integer and $1 \leq n \leq 10$.)

LINESPERPAGE/n/ Lines per page is optional. If it is omitted or greater than 63, 63 lines per page is assumed. When /n/ is present and less than 63, multiple copies of data pages are created to satisfy all 63 line flags.

INVENTORY/n/ Inventory is optional. If it is omitted, a value of 75 is assumed. When /n/ is present it defines the percentage of page fill, which controls inventory update; /n/ may contain the word "NO" to allow exclusion of inventory pages and processing.

A sample deck setup to create a permanent I-D-S data file follows. It consists of 480 pages in the complete I-D-S data file but it is created as four files, each with 120 pages.

1	8	16
\$	SNUMB	
\$	IDENT	
\$	FILSYS	
\$	IPRIVITY	

```

CRMST      IDSF0URYQUAD/IDSF0URYQUAD,PASSWORD/DATABASE/,
           SIZE/100/
CCREAT     IDSF0URYQUAD,PASSWORD/DATABASE/
USERID     IDSF0URYQUAD$DATABASE
CPOS       IDSF0URYQUAD
FCREAT/IDS/ QUAD01,BASESIZE/480/,RNG/1,120/,
           PAGESIZE/160/,LINESPERPAGE/32/,
           INVENTORY/25/,SIZE/13/,MODE/RAND/,
           DEVICE/DS3/
FCREAT/IDS/ QUAD02,BASESIZE/480/,RNG/121,240/,
           PAGESIZE/320/,LINESPERPAGE/63/,
           INVENTORY/75/,SIZE/11/,MODE/RAND/,
           DEVICE/ST1/
FCREAT/IDS/ QUAD03,BASESIZE/480/,RNG/241,360/,
           PAGESIZE/320/,LINESPERPAGE/63/,
           INVENTORY/75/,SIZE/11/,MODE/RAND/,
           DEVICE/DS2/
FCREAT/IDS/ QUAD04,BASESIZE/480/,RNG/361,480/,
           PAGESIZE/320/,LINESPERPAGE/63/,
           INVENTORY/75/,SIZE/11/,MODE/RAND/,
           DEVICE/DS2/

$          ENDJOB
***EOF

```

The above control cards will create an I-D-S data file structure as shown in Figure 24.




Figure 24. I-D-S Data File Structure

The name in the System Master Catalog is the USERID assigned by the CRMASST directive. This is the name I-D-S will use as the I-D-S data file name.

To have access to this I-D-S data file, the user must supply a \$ USERID control card in the execution deck setup. The I-D-S journal records will contain this name, which will be used by the I-D-S utility routine when restart and recovery is required.

Creating a Temporary I-D-S Data File

A temporary I-D-S data file is created by including IDS Create directives with the I-D-S execution activity. These directives are contained in the .Q data file.

The directive format is:

1	8	16
IDS	CREATE	attributes

The attributes are separated by commas.

The attribute names may be the complete name or the abbreviation.

FILECODE(FC)/fc/ File code is used to associate the attributes on this directive with the file code on the \$ "File" card such as:

```
$ DISC fc,lud,#random links
```

BASESIZE(BSSZ)/n/ Base size is required on at least one directive card submitted for an I-D-S execute. If multiple directives are submitted, the value of /n/ must be identical; /n/ defines the maximum size of the complete I-D-S data file; /n/ must be greater than or equal to 1 and less than or equal to 262143.

RANGE(RNG)/r1,r2/ Page-range is required to define the pages contained in a file; r1 and r2 are the beginning and ending page numbers respectively; r1 must be less than or equal to r2 and the value of r1 and r2 must be greater than or equal to 1 and less than or equal to 262143. This range may be either the complete I-D-S data file or it may be a portion.

PAGESIZE(PGSZ)/n/ Page size is optional. If it is omitted, a size of 320 words is assumed. When it is present, /n/ must be greater than or equal to 40 and less than or equal to 640. This allows a different page size in each subfile within the complete I-D-S data file.

When /n/ is present the actual page size used will be adjusted, if required, to reflect a multiple of sector size of the hardware device for this file. (For a DSU200 Magnetic Disc Subsystem, page size will be 40×2^n , where n is an integer and $1 \leq n \leq 4$. For a DSU270 or a DSU167 or for an MDS200 Magnetic Drum Subsystem, page size will be $64 \times n$, where n is an integer and $1 \leq n \leq 10$.)

LINESPERPAGE (LPP) /n/ Lines per page is optional. If it is omitted or greater than 63, 63 lines per page is assumed. When /n/ is present and less than 63, multiple copies of data pages are created to satisfy all 63 line flags.

INVENTORY (INV) /n/ Inventory is optional. If it is omitted, a value of 75 is assumed. When /n/ is present it defines the percentage of page fill, which controls inventory update; /n/ may contain the word "NO" to allow exclusion of inventory pages and processing.

The deck setup below will create a temporary I-D-S data file to be used by the I-D-S activity.

1	8	16
\$	SNUMB	
\$	IDENT	
\$	OBJECT	
	.	
	.	
\$	DKEND	
\$	EXECUTE	DUMP
\$	LIMITS	
\$	DISC	A1,A1S,13R
\$	DISC	A2,A2S,11R
\$	DISC	A3,A3S,11R
\$	DISC	A4,A4S,11R
\$	DATA	.Q
IDS	CREATE	FC/A1/,BSSZ/480/,RNG/1,120/,PGSZ/160/, LPP/32/,INV/25/
IDS	CREATE	FC/A2/,BSSZ/480/,RNG/121,240/,PGSZ/320/, LPP/63/,INV/75/
IDS	CREATE	FC/A3/,RNG/241,360/
IDS	CREATE	FC/A4/,RNG/361,480/
\$	ENDJOB	
***EOF		

Mixing Temporary and Permanent Files

An I-D-S data file is subordinate to the GECOS-III file system. The I-D-S data file may be created on one or many mass storage devices with different hardware characteristics. This facility allows selected I-D-S record types to be given page-ranges, which may then be directed to a specific hardware device when the file is created. I-D-S utility routines provide for selective file dump and reload. It is possible that an application may require that pages residing on one type of hardware be dumped and then reloaded on another type of hardware.

Two hypothetical cases where the user may want to mix permanent and temporary files follow:

A user may want to establish a page range for records that are only used weekly or monthly. For this application, the page range would not be created as a permanent file. Instead the page range would be created as a temporary file, the data stored, and the file dumped to tape.

When the records are to be used, the temporary file is established, the file is reloaded from the dumped tape, and the program is executed using this file in conjunction with the permanent file. Again, the file is dumped to tape and saved for the next weekly or monthly run.

Another example of mixed permanent and temporary files is using a temporary file for the work area of execute activities. In this usage, a permanent file would not be required for the delete process, since this temporary area would be purged at the end of the activity.

ACCESSING AN I-D-S FILE

Subfile Allocation

Each subfile requested must have been created previously as an I-D-S data file. A \$ PRMFL control card is required for each subfile. Refer to CPB-1518 for a complete discussion of options used. The I-D-S options are discussed below:

1	8	16
\$	PRMFL	fc,Permit,Mode,File String
\$	PRMFL	fc,/LUD,Permit,Mode,File String

PERMIT is an option describing the I-D-S usage. Multiple access modes may be used. If used, they are separated by slashes (/). The valid options are:

WRITE - The user requests the subfile for updating records.

READ - The user requests the subfile for retrieving records.

RECOVERY - The user requests access to an aborted subfile to reestablish the integrity of the subfile.

Examples:

1	8	16
\$	PRMFL	A1,READ,R,IDSFOURYQUAD/QUAD01
\$	PRMFL	A2,READ/WRITE,R,IDSFOURYQUAD/QUAD02
\$	PRMFL	A3,RECOVERY/READ/WRITE,R,IDSFOURYQUAD/QUAD03

Sample deck set up of LUD Option, used with the "CLOSE WITH LOCK" statement for dynamic release of I-D-S file.

1	8	16
\$	IDENT	
\$	USERID	
	.	
	.	(First Activity)
\$	PRMFL	A1/D1S,R/W,R,FILE STRING
\$	PRMFL	A2/D2S,R/W,R,FILE STRING
	.	
	.	(Last Activity)
\$	FILE	TF,D1R,1R
\$	FILE	TG,D2R,1R

Table A shows the action taken when the LUD option is used.

DISPOSITION CODE	PERMANENT FILE	TEMPORARY FILE
R	File is made unavailable to the run unit. File space is available to the system for allocation.	File is made unavailable to the run unit. File is available for allocation to other jobs.
S	File is made unavailable to the run unit. File space is held for allocation to other activities in this job.	File is made unavailable to the run unit. File is <u>NOT</u> available for allocation to other jobs. File is held for allocation to other activities in this job.

Table A.

An I-D-S activity which includes a request for subfiles is not allocated until all requested subfiles are allocated. The subfile allocation criteria are shown in Figure 25.

SUBFILE ALLOCATION CONDITION	ACCESS REQUESTED											
	READ				WRITE				RECOVERY			
FILE IN ABORT STATE	X				X				X			
FILE BUSY WRITE (UPDATE)		X				X				X		
FILE BUSY READ (RETRIEVE)			X				X				X	
FILE NOT BUSY				X				X				X
ACTION												
DENY ALLOCATION		X				X	X					
DELETE ALLOCATION REASON CODE	15				15				16	16	16	
PERMIT ALLOCATION			X	X				X	X			

Figure 25. I-D-S Data File Allocation

Since a READ access mode does not alter the contents of a subfile, several I-D-S activities can share a subfile in READ mode. If a subfile is allocated to an activity in the READ mode, it can also be allocated to any other I-D-S activity which wishes to use it in the READ mode. Allocation of the subfile would be denied, however, to any activity requesting WRITE usage for a subfile which is already allocated for READ usage.

While there can be concurrent users of a subfile in READ mode, there can be only one active user for a subfile in the WRITE access mode. All other allocation requests for the subfile would be denied until the activity which is doing the UPDATE has terminated.

Subfiles allocated in the WRITE access mode are marked in ABORT status if the activity aborts. A subfile in ABORT status will be allocated by requesting RECOVERY access mode in addition to READ and WRITE.

The individual responsible for maintaining the I-D-S data file must prepare the necessary input for a RECOVERY run. The utility routines which aid in this preparation are discussed later.

The abort indicator is turned off for an aborted subfile after a successful RECOVERY run is made on that subfile. It is then available for normal allocation.

Subfile Deallocation

I-D-S data files are deallocated at activity termination. Figure 26 shows the deallocation activity and the action taken.

ACTIVITY TERMINATION CONDITION	FILE BUSY ACCESS MODE					
	READ		WRITE		RECOVERY	
NORMAL	X		X		X	
ABNORMAL		X		X		X
ACTION						
SET FILE ABORT ON				X		X
SET FILE NORMAL	X	X	X		X	
SET FILE ABORT OFF					X	

Figure 26. I-D-S Data File Deallocation

I-D-S JOURNAL FILE

A journal file is a recording of all I-D-S data file page transactions. Journal information is collected on the accounting file tape from each of multiple I-D-S activities in execution, thus providing a single source file that is used to reestablish a data file to some previously known status in the event that the file should lose its integrity. A journal tape is labeled and is a single file. Multiple reel output may be produced depending on the journalization required.

When an end of reel is reached or an activity with write permission aborts, a reel swap or unit switch occurs. Two operator inputs permit the accounting file to be closed for I-D-S purposes:

- IDSEJ Close the accounting file with an EOF trailer label when all I-D-S jobs known to the system are complete.
- IDSER Close the accounting file with an EOR trailer label at the time of the request.

I-D-S Journal File Configuration

The I-D-S Journal file is configured on the system accounting file tape at system startup time by adding the I-D-S options to the Startup \$ ACCOUNT control card. Refer to the GE-600 Line GECOS III Startup Software Maintenance Document, CPB-1489.

The I-D-S options are:

IDS This option indicates that the I-D-S journal records are to be included on the system accounting file as record type 13(8).

BUFSIZ/n This option sets the size of the collecting buffers for I-D-S journal records and the accounting records. If omitted, then /n is assumed to be 320. The value /n must be set to at least 12 words larger than the maximum page size that may be placed on the journal file. If a journal record is encountered which is greater in size than the collecting buffer, the slave program will be terminated with a D2 abort code.

RETENTION/n This option allows the retention period in days required for label checking/writing to be established for the I-D-S journal file.

Journal Record Format

Journal records are produced as record type 13(8) on the system Error and Accounting file which must be configured at system startup time and must be assigned to magnetic tape. Override options are discussed later.

With the exception of block size, records are written in standard system format as described in the GE-600 Line File and Record Control Reference Manual, CPB-1003. The block size is as large as the buffer size defined on the startup \$ ACCOUNT control card.

The various formats for record type 13(8) that can be recorded on the journal tape appear below followed by definitions of terms common to all types.

Slave Begin Sync, Record Type 03. This record is written at the beginning of each I-D-S slave activity.

<u>Word</u>	<u>Contents</u>
1	Record control word for journalizing
2	Checksum
3	SNUMB
4	Start date (MMDDYY)
5	Start time (HH.TTT)
6	.Indicators (bits 0-11) Activity number (bits 27-35)
7	Not used
8 } 9 }	I-D-S data file name

Subroutine .QOPEN generates this record and stores it in the slave program prefix as follows. (See also "I-D-S Data Pages" in Chapter 7 for special conditions that apply when using disc sort.)

Location in
Prefix (decimal)

Word Contents

54
55
56
57
58
59
60
61
62

000010 (Size)	000013 (Type)
Checksum	
SNUMB	
MMDDYY	
HH.TTT	
030	Activity #
0	
I-D-S data file name	

Page Image Record, Record Types 05 and 06. There are two types of Page Image records (BEFORE and AFTER) written to the journal tape. The indicator word defines the type. A BEFORE page image is written before a page is modified. An AFTER page image is written after the modification.

Word

Contents

1 Record control word for journalizing
2 Checksum
3 Job number
4 Start date (MMDDYY)
5 Start time (HH.TTT)
6 Indicators (bits 0-11)
Activity number (bits 27-35)
7 Lines per page (bits 0-17)
Sequence number (bits 18-35)
8 }
9 } I-D-S data file name
10-n Activity page image

Slave End Sync, Record Type 04. This record is written when an I-D-S slave program terminates. The termination code is stored in the record.

Word


Contents

1 Record control word for journalizing
2 Checksum
3 Job number
4 Start date (MMDDYY)
5 Start time (HH.TTT)
6 Indicators (bits 0-11)
Activity number (bits 27-35)
7 Termination code
8 }
9 } I-D-S data file name

Journal Record, Record Type 09. This record is written when subroutine .QSTB is used to gather type B subroutine execution information. (See QUTR Program writeup in Chapter 8.)

<u>Word</u>	<u>Contents</u>
1	Record control word for journalizing
2	Checksum
3	Job number
4	Start date (MMDDYY)
5	Start time (HH.TTT)
6	Indicators (bits 0-11)
	Activity number (bits 27-35)
7	Alter number of call to subroutine
8	I-D-S data file name
9	
10	Control word (see following explanation)
11	Number of reads } for any given Number of writes } control word (word 10)
12	

The control word format (word 10) is as follows:



where:

Code is one of the following function values:

- 1 - Store record type
- 2 - Retrieve record type
- 3 - Retrieve current record type
- 4 - Retrieve direct
- 5 - Retrieve each
- 6 - Retrieve next of chain
- 7 - Retrieve prior of chain
- 8 - Retrieve master of chain
- 9 - Head of chain
- 10 - Modify record type
- 11 - Delete record type
- 12 - Debug

Type - 1 is the record type for the preceding function or the record type of the master of a chain.

Type - 2 is the record type of a detail of a chain.

Definition of Terms

Checksum	The checksum of all words (other than the checksum word) in the record.
Date	A 6-character field indicating month, day, and year the record was written. For slave End Sync records, it is the date the corresponding Slave Begin Sync record was written.
Time	Time the activity was started expressed in hours, decimal point, and thousandths of an hour in BCD format (HH.TTT). For Slave End Sync or Page Image records, it is the time in the corresponding Slave Begin Sync record.
Indicators	A 1-word indicator which defines the record type and contains the activity number.
Record Type	A 1-character BCD field that appears in bits 6-11 of the indicator word. The record type indicators are shown below: TYPE 3 Slave Begin Sync (SLVBGN) TYPE 4 Slave End Sync (SLVEND) TYPE 5 Before Page Image (BEFORE) TYPE 6 After Page Image (AFTER) TYPE 9 Statistics
Lines per Page	The lines per page for the Before/After Page Image.
Termination Code	A 2-character code in bits 27-35 of the Slave End Sync record. Termination codes are: 00 Normal activity termination 00 Normal job termination cc Abnormal termination; cc is a 2-character alphanumeric abort code.
I-D-S Date File-Name	A 12-character name, left justified. This name is taken from the \$ USERID card.

Job Number A 5-character SNUMB for the job, left justified and followed by an ignore character.

Activity Number A 9-bit binary job activity number.

Sequence Number A binary sequence number carried in the Page Image records. BEFORE records are sequenced by 1 in ascending order starting with 1. AFTER records are sequenced in descending order starting with all binary 1's in bits 18-35.

Record control word for journalizing A control word that contains the number of words in the record in bits 0-17 and defines it as record type 13(8), right-justified, in bits 18-35.

Closing Journal Files

The system-configured journal tape collects the journal data as one long file. From an operational point of view, it is necessary to periodically "close" one journal file and start another. This closing, followed by an opportunity to dismount and replace the journal tape, is done automatically when there is a master mode abort.

The operator may periodically request that a journal file be closed and another file started. He does this by requesting control and using the IDSEJ typein. The system response to this input is shown in the following table.

<u>CONDITION</u>	<u>ACTION</u>
An I-D-S activity is in execution.	IDSEJ DELAY message is typed out. The I-D-S journal file will be closed when there is no I-D-S activity in execution.
No I-D-S activity is in execution.	An end-of-file is recorded on the journal tape and a dismount message is issued.

Journal Override

Journal records are automatically written to the system-configured Error and Accounting tape; however, there are two activity override options available. Option 1 permits the user to request his own tape; option 2 suppresses all journalization.

The control card format for option 1 is:

1	8	16
\$	TAPE	JX,X1D,,,,IDS-JOURNAL

If a tape file JX is assigned for an activity, all journal record types -- the Slave Begin Sync, Slave End Sync, and all BEFORE and AFTER records and all statistics records -- are written to this file.

The control card format for option 2 is:

1	8	16
\$	EXECUTE	DEBUG

DEBUG in the variable field of the \$ EXECUTE control card causes bit 11 of the Program Switch Word to be set ON which prevents any journal records from being generated.

Examples:

1. The Slave Begin Sync, Slave End Sync, BEFORE and AFTER records are written to the user-supplied file JX.

1	8	16
\$	IDENT	
\$	OBJECT	
	.	
	.	
\$	DKEND	
\$	EXECUTE	Options
\$	TAPE	JX,X1D,,,,IDS-JOURNAL

2. No journalization takes place.

1	8	16
\$	IDENT	
\$	OBJECT	
	.	
	.	
	.	
\$	DKEND	
\$	EXECUTE	DEBUG
	.	
	.	
	.	

Journal File Map

A map of all Sync records contained on the I-D-S Journal file may be produced by executing the .QUTJ I-D-S utility routine (1) when a journal file has been made available after the abnormal termination of an I-D-S activity or, (2) the operator requests an end-of-file condition.

A sample journal file map follows.

QJNL 01 09-27-68 11,341		IDS JOURNAL TAPE REPORT					
IDS UTILITY ROUTINE - ,QUTJ - VERSION						080168,	
9	SLVBGN	1-QUTI	09-27-68	11,199	030	0	IDSFOURYQUAD
10	SLVEND	1-QUTI	09-27-68	11,199	040	00	IDSFOURYQUAD
15	SLVBGN	1-TST03	09-27-68	11,210	030	0	IDSFOURYQUAD
38	SLVBGN	1-TST3C	09-27-68	11,211	030	0	IDSFOURYQUAD
117	SLVEND	1-TST03	09-27-68	11,210	040	00	IDSFOURYQUAD
133	SLVEND	1-TST3C	09-27-68	11,211	040	00	IDSFOURYQUAD
138	SLVBGN	1-QUTDL	09-27-68	11,222	030	0	IDSFOURYQUAD
140	SLVEND	1-QUTDL	09-27-68	11,222	040	00	IDSFOURYQUAD
142	SLVBGN	2-QUTDL	09-27-68	11,227	030	0	IDSFOURYQUAD
143	SLVEND	2-QUTDL	09-27-68	11,227	040	00	IDSFOURYQUAD
149	SLVBGN	1-TST4A	09-27-68	11,237	030	0	IDSFOURYQUAD
150	SLVBGN	1-TST4B	09-27-68	11,238	030	0	IDSFOURYQUAD
151	SLVEND	1-TST4A	09-27-68	11,237	040	00	IDSFOURYQUAD
153	SLVEND	1-TST4B	09-27-68	11,238	040	00	IDSFOURYQUAD
155	SLVBGN	1-TST4C	09-27-68	11,240	030	0	IDSFOURYQUAD
156	SLVEND	1-TST4C	09-27-68	11,240	040	00	IDSFOURYQUAD
161	SLVBGN	1-QUTD	09-27-68	11,247	030	0	IDSFOURYQUAD
162	SLVEND	1-QUTD	09-27-68	11,247	040	00	IDSFOURYQUAD

RECOVERING AN I-D-S DATA FILE

All I-D-S slave programs interface with GECOS-III through the MME GEIDSE incorporated in the I-D-S object-time subroutines. The MME enables the subroutines to record page images on a system configured journal tape. BEFORE page images are written to the journal tape prior to the modification of a page; AFTER page images are written to the journal tape following modification of the page. When recovery of the data file is desired, the journal tapes containing the required pages are processed as illustrated in Figure 27A. Figure 27B illustrates an alternate method.




Figure 27A. Operational Sequence to Re-establish an I-D-S Data File




Figure 27B. Alternate Operation to Re-establish an I-D-S Data File

The individuals responsible for maintaining the data base establish the selection criteria for obtaining the appropriate pages from the journal tape. This is done using the information from the Journal Tape Map or from a complete journal dump created by the QUTJ utility routine. The QUTP utility routine selects pages from the journal tape. The QUTS utility routine then sorts the selected page image records and purges multiple page images having the same page number. The sorted output consists of the first BEFORE or the last AFTER image for a given page number as required for the data file reload. The QUTU utility routine reloads the output to the appropriate portions of the data file.

Since rollback does not reestablish the data file to a previous condition, the MME GECHEK and MME GEROLL should not be used by an I-D-S program.

I-D-S EXECUTION REPORT

I-D-S appends information about the data base to the execution report. This information includes (1) the attributes of the data base (2) total input/output performed on the data base, and (3) input/output performed on the data base as a function of each I-D-S subroutine. Formats of the three types of information are shown in the following examples and are explained by the notes corresponding to the circled callouts.

Example 1: Data Base Attributes

- ① Files Allocated -- the number of permanent and/or temporary IDS files allocated to the activity
- ② Range -- the smallest and largest page number present in the files
- ③ Basesize -- the value to be used in the randomize routine
- ④ Buffers -- the number of page buffers present

An entry appears under each of the following heads for each file or subfile:

- ⑤ Filecode -- the file code referenced by the program
- ⑥ Range -- the range for this file or subfile

- ⑦ Pagesize -- the page size for this file or subfile
- ⑧ Pages/Page -- the number of pages per page for the file or subfile
- ⑨ Lines/Page -- the number of lines per page for the file or subfile
- ⑩ Links Alloc -- the number of links allocated to the file or subfile
- ⑪ Links Nec -- the number of links necessary to contain the pages defined for the file or subfile
- ⑫ Access Mode -- the mode in which the file or subfile is being accessed
- ⑬ Inventory -- the percentage value at which inventory will be updated on the file or subfile

① ② ③ ④

1 FILES ALLOCATED, RANGE 1 - 100 BASESIZE 100 BUFFERS 29

FILECODE	RANGE	PAGESIZE	PAGES/PAGE	LINES/PAGE	LINKS ALOC	LINKS NEC	ACCESS MODE	INVENTORY
A1	1- 100	320	1	63	20	9	WRITE	75
⑤	⑥	⑦	⑧	⑨	⑩	⑪	⑫	⑬

Example 2: Total I/O Performed on Data Base

The following are shown for each file or subfile:

- ① File Code -- the file code referenced by the program
- ② # of Reads -- the total number of reads that occurred on the file or subfile
- ③ # of Writes -- the total number of writes that occurred on the file or subfile
- ④ Inventory Reads -- the number of inventory reads that occurred on the file or subfile
- ⑤ Inventory Writes -- the number of inventory writes that occurred on the file or subfile

I-D-S UTILIZATION REPORT

FILE CODE	# OF READS	# OF WRITERS	INVENTORY READS	INVENTORY WRITES
TF	258	2883	1	1
①	②	③	④	⑤

Example 3: I/O Performed on Data Base as a Function of Each I-D-S Subroutine

This report is produced by the I-D-S close subroutine. Counts are accumulated for each primary entry subroutine -- that is, each subroutine called by the object program. These are known as type A (.QSTA) subroutine execution statistics. (An additional, more detailed (type B) report can also be produced as a separate output at the user's option. For this report the .QSTB subroutine is used to accumulate the statistics on the journal file, and the QUTR program produces the report. See the QUTR writeup in Chapter 8 for details.)

The type A report contains the following information:

- ① Primary entry subroutine name
- ② Total number of times subroutine was called
- ③ Total number of reads for execution of the subroutine
- ④ Total number of writes for execution of the subroutine

SUBROUTINE STATISTICS

NAME	NO. TIMES CALLED	NO. READS	NO. WRITES
.QSTOR	18	6	10
.QGET	18	0	2
.QCHN	88	0	6
.QMDFY	18	0	24

①	②	③	④
---	---	---	---

7. Memory Management

ASSIGNMENT OF I-D-S BUFFERS AND WORK AREAS

The I-D-S subroutines require data page buffer areas and working areas. The user defines the size of these areas by employing one of the two following procedures.

With a \$ USE Card

A Labeled Common area (.QAREA) may be specified by the GELOAD control card shown below:

1	8	16
\$	USE	.QMAX/1/, .QAREA/n/, .QMIN/1/

The \$ USE control card must be inserted before the \$ EXECUTE card in the object deck so that GELOAD will encounter it prior to loading the I-D-S subroutines from the library. Refer to the GE-600 Line General Loader Reference Manual, CPB-1008.

The value supplied for /n/ must be large enough to contain the working area plus at least three page buffers. The following formula may be used to determine the total space required.

$$(NF*10) + 10 + ((MP + 21)*NB) + NO + (I + 3)$$

where NF is the number of files allocated
MP is maximum page size allocated in words
*NB is number of page buffers
I is maximum sector size for files containing inventory. (For DSU200, I = 40; for all other mass storage devices I = 64.)
*NO is number of page buffers which overlay .QOPEN.

*The total number of buffers (TB) must be at least three. TB = NB+NO, where NO is determined by the following formula:

$$NO = 816/(MP+20)$$

When a sort is included as part of an I-D-S activity, a \$ USE card must be used to constrain the work area of one of the systems. If this is not done, both systems will compete for the area not assigned to other program segments.

A sample deck setup for an I-D-S sort using disc sort and temporary I-D-S files follows. With this setup, the sort work area will be the core storage remaining from the \$ LIMITS card after subtracting the user program size and the I-D-S page buffer size (.QAREA).

1	8	16
\$	IDENT	
\$	USE	.QMAX/1/, .QAREA/5000/, .QMIN/1/
\$	OBJECT	USERPROGRAM
\$	EXECUTE	
\$	LIMITS	10, 32K
\$	DISC	TF,D1S,10R
\$	DISC	S1,X1R,5R
\$	DATA	.Q
IDS	CREATE	FC/TF/,BSSZ/100/,RNG/1,100/
\$	ENDJOB	
***EOF		

Without a \$ USE Card

When the \$ USE control card procedure is not used, the .QOPEN I-D-S subroutine attempts to use the area in memory not assigned to other program segments. The size of this available area is inserted in word 37(8) of the slave program prefix by GELoad during the loading process. As in the procedure above, the available area is divided into a work area and some number of buffers, depending on the size of the area. A minimum of three buffers must be established or the slave program will be terminated. The .QOPEN subroutine modifies the content of word 37(8) to reflect the usage of this area.

When the file is opened, the size of .QAREA is determined and then used in the following manner (see Figure 28):

1. Slave I-D-S Control Table - this table consists of 10 control words plus 10 words for each I-D-S subfile (temporary or permanent) assigned to the activity.
2. Inventory Record Buffer - this area is equal to three words more than the largest inventory sector allocated.
3. Page Buffer Activity Table - this table contains one word for each page buffer.

4. Data Page Buffers - these buffers are equal to the page size of the largest page allocated plus 20 decimal words.
5. The first inventory buffer exists as defined in Figure 28. The other inventory buffers and their headers are generated by .QOPEN and overlay the code in .QOPEN that may be executed only once. As many buffers exist as will fit in the overlay area.




Figure 28. Labeled Common .QAREA

SLAVE I-D-S CONTROL TABLE

Figure 29 shows a Slave I-D-S Control Table used by the I-D-S subroutines to honor the attributes of an I-D-S data file. Each subfile may be different, such as page size and percent of page fill for inventory. The I-D-S subroutines use a common GEFRC file control block to do all I-D-S data page and inventory page I/O on the mass storage. To accomplish this, the file control block control information is kept in the SICT Table for each unique file. It is then placed into the file control block when an I/O request for a page is needed. The total length of the table is dependent on the number of files allocated.

Bits 0	1718	35	
Word 0	Pointer to Current Entry	MBZ	 Total Control Entry
1	Maximum Page Size	Base Size	
2	Lowest Page Number	Highest Page Number	
3	Maximum Inventory Sector	Page Buffer Size	
4	 MBZ	 MBZ	
5			
6			
7	 MBZ	 MBZ	
8			
9	MBZ	Count of Entries	
0	RANGE R1	RANGE R2	 File Control
1	Inventory Write Counter	Page Size	
2	Pages/Page No.	Lines Per Page	
3	RBA of Current Inventory	Inventory Percent Fill	
4	Inventory Read Counter	RBA Current Page	
5	Sectors/Page	Sector Size	
6	Gross Write Counter	Gross Read Counter	
7	Base RBA of Inventory	FILCB+0 [18-35]	
8	FILCB-5 [18-35]	FILCB-1 [18-35]	
9	Access Mode	FILCB-4 [24-35]	

Figure 29. Slave I-D-S Control Table

The description of the Slave I-D-S Control Table (SICT) follows.

Total Control Entry

Word 0

bits

0-17 Pointer to current entry - the address of the SICT table entry which contains the relative block address of the page number last requested via the I-D-S mapping subroutine.

18-35 Must be zero.

Word 1

bits

0-17 Maximum page size - the value in words of the largest page size allocated.

18-35 Base size - the total number of pages in the I-D-S data file.

Word 2

bits

0-17 Lowest page number - the lowest page number allocated.

18-35 Highest page number - the highest page number allocated. Must be less than or equal to the value in the base size.

Word 3

bits

0-17 Maximum inventory sector - the size in words of the largest inventory sector allocated.

18-35 Page buffer size - the maximum page size plus 20 decimal to include the page header area.

Word 4
through
Word 8

Must be zero.

Word 9

bits

0-17 Must be zero.

18-35 Count of entries - the number of subfiles allocated to form this I-D-S data file.

Individual File Entries

Word 0

bits

- 0-17 RANGE R1 - the lowest page number assigned to the subfile.
- 18-35 RANGE R2 - the highest page number assigned to the subfile. R2 must be greater than or equal to R1.

Word 1

bits

- 0-17 Inventory write counter - a counter for the number of times an inventory record has been written to the file.
- 18-35 Page size - the page size in words defined for the file. The page size must be greater than or equal to 40 and less than or equal to 640.

Word 2

bits

- 0-17 Pages/page No. - the number of pages as developed by dividing 63 by the number of lines per page.
- 18-35 Lines per page - the number of lines that may be used in any page or pagette.

Word 3

bits

- 0-17 RBA of current inventory - the Relative Block Address (RBA) of the current inventory record. Inventory records are physically stored beginning in the first sector, following the last data page of the file.
- 18-35 Inventory percent fill - the number of characters that may be placed in a page of this file before the inventory adjustment routines are called. If the value is negative (bit 18=1), there are no inventory records, therefore, there is no inventory processing.

Word 4

bits

- 0-17 Inventory read counter - a counter for the number of times an inventory record has been read from this file.
- 18-35 RBA current page - the Relative Block Address of the last page number accessed in this subfile.

Word 5
bits
0-17 Sectors/Page - the number of sectors within a page. The size is calculated by dividing sector size of the mass storage device into the page size.

18-35 Sector size - the sector size of the hardware device of this file.

Word 6
bits
0-17 Gross write counter - a counter for the number of times data pages or inventory records have been written to the file.

18-35 Gross read counter - counter for the number of times data pages or inventory records have been read from the file.

Word 7
bits
0-17 Base RBA of inventory - relative block address of the beginning of inventory for the file.

18-35 FILCB+0 - contents of the GEFRC file control block.

Word 8
bits
0-17 FILCB-5 (18-35) - contents of the GEFRC file control block.

18-35 FILCB-1 (18-35) - contents of the GEFRC file control block.

Word 9
bits
0-17 Access mode - the access permissions requested from the \$ PRMFL card for this file or the permissions granted for the \$ DISC or the \$ MASS control card for this file.

Bits 0 READ (RETRIEVE)
1 WRITE (UPDATE)
2 Not used by I-D-S
3 RECOVERY
4-17 Not used by I-D-S

18-35 FILCB-4 (24-35) - file code for the file.

I-D-S INVENTORY RECORDS

To minimize mass storage seek and transfer time, a number of inventory records are maintained in numerous buffers in memory.

Buffer Format

The I-D-S inventory record buffer format is shown in Figure 30.




Figure 30. Inventory Record Buffer

A description of the Inventory Record buffer follows:

INVENTORY RECORD WORD AREA

- Word 0 bits
 - 0-17 Address of the next Inventory buffer header (this list is circular).
 - 18-35 The number of this buffer (starting at 0).
- Word 1 bits
 - 0-11 Must be zero.
 - 12-35 The beginning reference code of the Inventory record in the buffer.
 - Bits 12 - 29 Page number
 - 30 - 35 Line number

Word 2
bits
0-11 Must be zero.

12-35 The ending reference code of the Inventory record in the buffer.

Bits 12 - 29 Page number
30 - 35 Line number

Word 3
through
word n Inventory record area.

Buffer Strategy for Inventory Buffer

If the inventory is needed for a page and the inventory record is not in memory, it is read into the inventory buffer defined as empty; and words 1 and 2 of the buffer header are updated.

The next inventory buffer as defined by word 0 of the header is then established as the empty buffer. Its contents are written back to the data file if the contents have been altered.

Record Description

Inventory records are physically stored at the end of the file for the page-range specified. They are record type 1002(10). The Inventory record size is equal to the sector size of the device on which it is stored. Thus the number of pages covered by one Inventory record is variable; it is equal to $3 \times (\text{sector size} - 2)$. On a DSU204 one link holds inventory for 10,944 pages; on a DSU270 or a DSU167 one link holds inventory for 11,160 pages.

The initial inventory of space available will be the page size (in characters) less the space occupied by the Page Header record (22 characters).

The Inventory record format is shown in Figure 31.




Figure 31. Inventory Record

The bit configuration for an Inventory record follows:

- Word 0
bits
- 0-17 Beginning page number that is contained in the Inventory record.
 - 18 Must-Write switch - an indicator used by I-D-S subroutines to determine if this record has been modified since retrieval.
 - 19 Must be zero.
 - 20-29 Record type - a value of 1002 (10) assigned to each Inventory record.
 - 30-35 Beginning line number of the beginning page for this Inventory record.
- Word 1
bits
- 0-11 Must be zero.
 - 12-35 Ending Reference Code that is contained in this Inventory record.
- Bits 12 - 29 Page number
Bits 30 - 35 Line number

Word 2

bits

- 0-11 Space available in characters for the Reference Code contained in word 0, bits 0-17 and 30-35.
- 12-23 Space available for the next ascending page (this may be a pagette).
- 24-35 Space available for the next page.

Word 2 is repeated for consecutive pages until bits 24-35 of word n is the space, in characters, available in the page defined by the ending reference code (bits 12-35 of word 1).

I-D-S DATA PAGES

To minimize mass storage seek and transfer time, a number of data pages are maintained in numerous buffers in memory. The number of buffers depends on the amount of space available in .QAREA after loading the program.

The greater the number of data pages kept in memory, the greater the possibility that the one needed next will already be there. To further improve the possibility of finding the page desired in memory, the I-D-S subroutines keep track of page utilization (record activity) and hold the most recently active pages in memory. Pages infrequently accessed are retired from memory as others are called in. The I-D-S subroutines note which pages have been modified and only the modified pages are written back to mass storage.

Buffer Format

The I-D-S page buffer format is shown in Figure 32.

The description of the Data Page Buffer follows.

PAGE HEADER WORK AREA

Word 0
bits

- 0-17 Pointer to the next buffer. This will be zero in the last buffer.
- 18-35 Buffer number - the number of the buffer beginning with zero.

Word 1
bits

- 0-11 Must be zero.
- 12-35 The beginning reference code of the I-D-S data page in the buffer.
- Bits 12 - 29 Page number
30 - 35 Line number

Word 2
bits

- 0-11 Must be zero.
- 12-35 The ending reference code of the I-D-S data page in the buffer.
- Bits 12 - 29 Page number
30 - 35 Line number

Word 3
bits

- 0-23 Must be zero.
- 24-35 Character space available in the I-D-S data page when read from the mass storage device.




Figure 32. Data Page Buffer

Word 4
bits
0-35 Available line flag indicator of the I-D-S data page when read from the mass storage device.

= 0 line flags available
≠ 0 line flags not available

Word 5
through
Word 7 Must be zero.

JOURNAL TAPE CONTROL AREA

Word 8
through
Word 10 Work area for GEFRC I/O control - contains an I/O control word, Block Serial number and Record Control word.

Word 11
bits
0-17 Contains the number of words in the record when written to the journal tape.

18-35 Contains the value 13(8) to define the accounting record type.

Word 12
bits
0-35 Checksum - all words (other than the checksum word) in the record.

Word 13
bits
0-35 Job number - the five character SNUMB for the job, left justified and followed by an ignore character.

Word 14
bits
0-35 Start date - month, day, year the activity started, in BCD format (MMDDYY).

Word 15
bits
0-35 Start time - time the activity started expressed in hours, decimal point, and thousandths of an hour in BCD format (HH.TTT).

Word 16
bits
0-5 Must be zero.

6-11 A 1-character BCD field that defines the journal record type.

 Type 5 Before Page Image (BEFORE)
 Type 6 After Page Image (AFTER)

12-26 Must be zero.

27-35 Activity number - a 9-bit binary job activity number.

Word 17
bits
0-17 Lines per page for the Before/After Page Image.

18-35 Sequence number - a binary sequence number. BEFORE records
are incremented by 1, starting with 1. AFTER records are
decremented by 1, starting with -1.

Word 18
through
Word 19
bits
0-35 I-D-S Data File Name - a 12-character name left justified.

I-D-S DATA PAGE AREA

Word 20
through
Word n
The area which contains the I-D-S data page when read from the
mass storage device.

Buffer Strategy for Page Buffers

Each time a page is brought into memory its buffer number is placed at the head of a buffer table. If a page already in memory is used again, its buffer number moves to the head of the table. Thus, the most frequently used pages are at the top of the table and the pages with little or no recent use are at the bottom of the table. Buffer space is always available for reading a data page. To make a buffer available, the page at the bottom of the list is written back to the mass storage device, provided there has been activity updating that page. This buffer is called the EMPTY buffer; it is the buffer with lowest activity.

The order of the chain is defined in an Page Buffer Activity Table (Figure 33) which contains one word for each page buffer in .QAREA. The activity chain shown in Figure 34 is a closed circular loop of buffer numbers.

There is always an EMPTY buffer whose NEXT is the buffer of highest activity.

The PRIOR of the buffer of highest activity is the EMPTY buffer.

The other buffers in the Page Buffer Activity Table have, in the PRIOR column (bits 0-17), the buffer number of the next higher (more recent) activity. The NEXT column (bits 18-35) contains the buffer number of the next lower (less recent) activity.

For example, if buffer 5 is the EMPTY buffer, then buffer 4 is the most active buffer.

Buffer Number	0	PRIOR	1718	NEXT	35
0			4		2
1			3		5
2			0		3
3			2		1
4			5		0
5			1		4

Figure 33. Page Buffer Activity Table




Figure 34. Chain Concept of Buffer Activity

Page Description

There are two types of I-D-S data pages:

Base Page
I-D-S Page

The I-D-S data page consists of a fixed size which is assigned when the I-D-S file is created. It may contain any combination of logical record types linked into their respective chains. Each type has its own specific length. Related record types are associated and linked according to their data content and may be stored within the same page. Space is fully utilized by packing these records within the page.

Every page begins with a unique Page Header record. This record contains several control fields used by the I-D-S subroutines, as follows:

1. Reference address of the page (page number).
2. Space available for additional records.
3. I/O control indicating whether the page has been altered since retrieval.
4. Chain field indicating reference code of the first record of a chain of calculated records, all of which randomize to this page.
5. Line numbers available for assignment within the page.

Base Page. The format of the Base Page Header record is shown in Figure 35.




Figure 35. Base Page Header Record

The bit configuration for the Base Page Header record follows:

Word 0

bits

- 0-17 Reference code page number - a number from 1 through 262,143. During file initialization, each page requested by the user is assigned a unique number within this range.
- 18 Must-Write switch - an indicator used by I-D-S to determine if a page has been altered since retrieval.
- 19 Before-Image switch - an indicator used by I-D-S to indicate that a page to be modified has been written to the journal tape prior to the modification.
- 20-29 Record type - a code of 1000(10) assigned to each Page Header record.
- 30-35 First character of the CALC chain NEXT Link - a pointer to the first CALC record contained in the chain. If no CALC records are present, it points to itself. (The Page Header record is the defined master of the CALC chain.)

Word 1

bits

- 0-17 CALC Chain NEXT Link
- 18-29 Space available - current status of available space for storing records within a page.
- 30-35 Available line number flags (0-5) - an indicator used by I-D-S to determine line numbers available for assignment within a page:
 - 0 = line number available
 - 1 = line number not available

There are 64 line number flags. They are numbered left to right starting with zero. Line number 0 is always used; it is line number of the Page Header record. A maximum of 63 data records can be stored to a page.

Word 2

bits

- 0-35 Available line number flags (6-41)

Word 3

bits

0-21 Available line number flags (42-63).

22-23 Must be zero.

End of Page Header record. The length of the record is 22 characters.

24-35

through

word n Bits 24-35 of word 3 through bit 35 of word n contain data records.

Pagette. A pagette is introduced by setting the value of lines per page to less than 63. By dividing the lines per page into 63, the number of pages required to hold 63 line flags is developed. The first of these pages is called the BASE page. It contains a Page Header record (type 1000 decimal) which is the master record of the CALC chain for this page number. The remaining pages are called PAGETTES. They contain a Pagette Header record (type 1003 decimal). They are not the master of any chain.

The available line number flags begin in the base page. For example, if the lines per page equal 21, this would require $(63/21=3)$ pages to hold the 63 line number flags. Pages will have the line number flags set off for line numbers not allowed in the page. Thus, a base page will have line number flags as follows:

1 - 21 Available
22 - 63 Not available

Pagette number 1 will have:

1 - 21 Not available
22 - 42 Available
43 - 63 Not available

Pagette number 2 will have:

1 - 42 Not available
43 - 63 Available

The pagette allows users to increase the number of reference codes in their I-D-S data file. This facility is probably most useful on some portion of the total file that has been filled by large records.

For example, let record size be equal to the available space in a page such that one logical record fills a page. This record may be a dictionary record. When this record is stored the user eliminates 62 available reference codes. Thus, if several records are stored, several hundred potential reference codes are eliminated.

The user may choose to increase the page size such that several large records may fit into a single page, but practical limits on page size must be observed. Thus, the next approach may be to limit the lines per page, making available all 63 lines (reference codes) for each page.

The Pagette Header record format is shown in Figure 36.




Figure 36. Pagette Header Record

The bit configuration for the Pagette Header record follows:

- Word 0
bits
- 0-17 Reference code pagette number - a number from 1 through 262,143. During initialization, each pagette is assigned a unique number within this range.
 - 18 Must-Write switch - an indicator used by the I-D-S subroutines to determine if a pagette has been modified since retrieval.

19 Before-Image switch - an indicator used by the I-D-S subroutines to indicate that a pagette has been written to the journal tape prior to modification.

20-29 Record type - a value of 1003 (10) assigned to each Pagette Header record.

30-35 First character of the pagette number, which forms the beginning reference code.

Word 1
bits

0-11 Last two characters of the pagette number, which forms the beginning reference code.

12-17 Beginning line number of pagette - first available line number that may be placed in the pagette.

18-29 Space available - characters of available space for storing records within the pagette.

30-35 Available line number flags (0 through 5) - an indicator used by I-D-S to determine which line numbers are available for assignment within a pagette:

0 = line number available
1 = line number not available

There are 64 line number flags. They are numbered left to right starting with 0. Line number 0 is always used; it is the number of the Pagette Header record.

Word 2
bits

0-35 Available line number flags (6-41)

Word 3
bits

0-21 Available line number flags (42-63)

22-23 Must be zero.

End of Pagette Header record. The length of the record is 22 characters.

24-35
through
word n

Bits 24-35 of word 3 through bit 35 of word n contain data records.

I-D-S DATA RECORDS

Data records of I-D-S are fixed-format, fixed-length; that is, the length and format of a specific type of record, such as payroll or inventory, are fixed by the specifications of the systems designer. Records of many different types, each with its own length and format, may be used in the system. To maintain control, each record must have the same identification fields at the beginning. These fields are (1) line number portion of the reference code, (2) record type and (3) record length. The rest of the record consists of data and chain fields to suit the application requirements.

Records may have any number of data fields, each defined as some number of decimal, alphabetic or alphanumeric characters. Fields may vary in size from one character to many characters, as for a drawing or part number or an employee's name. These fields must be specified by the systems designer.

The format of the data record is shown in Figure 37.




Figure 37. Data Record

The bit configuration for a data record follows:

Word 0

bits

- 0-5 Line number - a number from 1 to 63. A unique number is assigned to each data record as it is stored in a page. This number combined with the page number from the Page Header record completes the reference code.
- 6 Delete switch - an indicator used by the I-D-S subroutines to recognize a record that is logically but not physically deleted. When all chain pointers in a record are equal to zero, the record will then be physically deleted and its line number will be made available for use in the page.
- 7-17 Record type - a unique number from 1 to 999 used to identify different kinds of data records. The numbers 1000 and greater are reserved for use by I-D-S.
- 18-29 Record size - the number of characters in the record including all control fields, data fields and chain pointers. The line number is character 1 of a record.

30-35 and

Word 1

bits

0-17

CALC chain NEXT - the reference code of the NEXT record in the CALC chain. If this is the last record in the CALC chain, it will contain a reference code of the Page Header record which is the master of this CALC chain. The chain pointer defined as detail of CALC chains. All other records do not contain this pointer and the data begins in this area.

Bits 30-35 and

0-11 Page number

12-17 Line number

18-35
through
word n

Beginning of available space for data characters. The data may be n characters in length.

Word n

bits

0-23

The Chain pointers begin in the character position immediately following the last data character.

The chain pointer reference code is 24 bits in length.

Bits 0-17 Page number

18-23 Line number

There may not be any chain pointers in the record if it is not a member of any chain, such as a Primary record; or the only pointer may be the CALC chain NEXT. The presence of chain pointers is dependent on the description of the I-D-S record. The type of chain pointer, NEXT, PRIOR, HEAD, and the chain it is pointer for is described in the definition structure associated with this record type.

8. I-D-S Utility Programs and Subroutines

The following I-D-S utility programs and utility subroutines are described in this chapter:

Programs:

- Randomizing Analyzer/Calc Pre-Load Sort Utility Program (QUTC)
- Storage Tape Dump/Print Routine (QUTD)
- Page Initialize Utility Routine (QUTI)
- Journal Tape Dump (QUTJ)
- Data Base Load/Print Utility Routine (QUTL)
- Journal Record Selector (QUTP)
- Execution Information Report (QUTR)
- Selected Record Sort (QUTS)
- File Utility (QUTU)

Subroutines:

- Directive Processor (.QDIR)
- Trace and Print Record (.QSTC)
- Verify and Print (.QUTF)

I-D-S execution activities may require that permanent, temporary, or a mixture of an I-D-S data file be used. The following examples of deck setups may be applied to all I-D-S utility programs and subroutines and user execute activities.

PERMANENT I-D-S DATA FILE

The following deck setup is for a permanent I-D-S data file.

1	8	16
\$	IDENT	IDS00,DATABASEMGR, PERM IDS FILE
\$	USERID	IDSFOURYQUAD\$DATABASE
	.	
\$	PRMFL	A1,R/W,R,IDSFOURYQUAD/QUAD01
\$	PRMFL	A2,R/W,R,IDSFOURYQUAD/QUAD02
\$	PRMFL	A3,R/W,R,IDSFOURYQUAD/QUAD03
\$	PRMFL	A4,R/W,R,IDSFOURYQUAD/QUAD04
	.	
	.	
\$	ENDJOB	
***EOF		

TEMPORARY I-D-S DATA FILE

The following deck setup is for a temporary I-D-S data file.

1	8	16
\$	IDENT	IDS00,DATABASEMGR, TEMP IDS FILE
	.	
	.	
\$	MASS	A1,X1S,13R
\$	DISC	A2,X2S,11R
\$	DRUM	A3,X3S,11R
\$	MASS	A4,X4S,11R
\$	DATA	.Q
IDS	CREATE	FC/A1/,BASESIZE/480/,RANGE/1,120/, PAGE SIZE/160/,LINESPERPAGE/32/, INVENTORY/25/
IDS	CREATE	FC/A2/,BSSZ/480/,RNG/121,240/,PGSZ/320/
IDS	CREATE	FC/A3/,RNG/241,360/
IDS	CREATE	FC/A4/,RNG/361,480/,PAGE SIZE/64/,LPP/15/
\$	DATA	I*
	.	
	.	
\$	ENDJOB	
***EOF		

TEMPORARY AND PERMANENT I-D-S DATA FILE

The following deck setup is for a mixed temporary and permanent I-D-S data file.

The permanent I-D-S data file attributes were supplied when the file was created; the temporary attributes must agree with the permanent attributes.

1	8	16
\$	IDENT	IDS00,DATABASEMGR, MIXED IDS FILE
\$	USERID	IDSF0URYQUAD\$DATABASE
	.	
\$	PRMFL	A1,R/W,R,IDSF0URYQUAD/QUAD01
\$	MASS	A2,X2S,11R
\$	DISC	A3,X3S,11R
\$	PRMFL	A4,R/W,R,IDSF0URYQUAD/QUAD04
\$	DATA	.Q
IDS	CREATE	FC/A2/,BSSZ/480/,RNG/121,240/,PGSZ/320/
IDS	CREATE	FC/A3/,RNG/241,360/
\$	DATA	I*
	.	
\$	ENDJOB	
***EOF		

UTILITY PROGRAM AND SUBROUTINE DESCRIPTIONS

Descriptions of the I-D-S utility programs and utility subroutines are presented on the following pages.

QUTC

Randomizing Analyzer/CALC Pre-Load Sort Utility Program (QUTC)

The QUTC utility program performs two distinct functions depending upon the directive option chosen.

1. The ANAL option utilizes the user supplied directive cards to generate numbers which are randomized to produce base page numbers and the total number of times each base page number is returned by the CALC routine. This information is printed on the Base Page Report. In addition, should the page number occur more than 63 (maximum lines per page) times, or any smaller number supplied by the user, this and the page number of the first page having space available will be indicated on the Overflow Report.
2. The RAND or RANDA option is used to sort CALC records into base page sequence prior to loading the data base. The user's input file must contain only one record type and must be in system standard format. A minimum of one control field for randomizing must be specified and a maximum of three control fields may be specified. These control fields must appear on the directive card in the order in which randomization is to be performed.

The total number of records randomizing to each page is accumulated and printed on the Base Page Report. In addition, a control for overflow is maintained which forces all overflow records to be sorted to the end of the file. The page which has overflow and the first page with space available is indicated on the Overflow Report.

Printing of these two reports may be suppressed by use of the RAND option.

Directive

General Format:

1	8	16
IDS	OPTION	GENERATE/,OPTION/,
	ETC	CONTROL/OPTION/,
	ETC	CONTROL/OPTION/,
		...

ANAL OPTION

This option generates page numbers based on control parameters explained below.

INPUT:
Directive cards

OUTPUT:
IDS BASE PAGE REPORT
IDS OVERFLOW REPORT

Control for ANAL option on directive card:

- RNG/P1,P2/ Specifies the page range to be analyzed.
- MAX/nm...n/ Specifies the largest number to be randomized.
- INCR/nm...n/ Specifies the increment to be added for each iteration.
- FILL/nm/ Specifies the point at which the page will be considered full.

Example:

1	8	16
IDS	OPTION	GENERATE/,ANAL/,
	ETC	RNG/1,100000/,MAX/50000/,
	ETC	INCR/2/,FILL/32/

RANDA OPTION

This option takes a user's file of CALC records, randomizes on specified control fields, producing a base page number, sorts the file into page number sequence with all overflow records sorted to the end of the file and produces two reports.

INPUT:
USER's CALC file
Directive cards

OUTPUT:
Sorted CALC file
IDS BASE PAGE REPORT
IDS OVERFLOW REPORT

Control for RANDA option on directive card:

- RNG/P1,P2/ Specifies the page range into which records are to be stored.

CF/C1,L1/ Specifies fields to be used for randomizing.

C1 reflects the beginning character of the field relative to one.

L1 reflects the lengths in characters of the control field.

A minimum of one control field must be specified and a maximum of three may be given.

FILL/nn/ Specifies the point at which a page will be considered full. If this parameter is not supplied 63 records per page is assumed.

Example:

1	8	16
IDS	OPTION	GENERATE/,RANDA/,RNG/500,1000/,
	ETC	CF/2,6/,CF/20,5/,CF/10,2/,
	ETC	FILL/63/

RAND OPTION

This option has the same effect as the RANDA option with the exception that no reports are produced.

Example:

1	8	16
IDS	OPTION	GENERATE/,RAND/,RNG/10,200/,
	ETC	CF/8,10/,FILL/8/

Directive Restrictions

1. Directives are examined to ensure that columns 1-3 contain IDS, that columns 8-13 contain OPTION and that the first parameter in the variable field is GENERATE.
2. All control parameters are required with the exception of FILL. This is assumed to be 63 when not specified.

Operation

1. Deck Setup for RANDA Option:

1	8	16
\$	IDENT	WTA00,YOUNGMAN,K72
\$	PROGRAM	QUTI Activity 1.
* \$	MASS	A1,D1S,10R
\$	DATA	.Q
*** IDS	CREATE	FC/A1/,BSSZ/100/,RNG/1,100/
\$	DATA	I*
IDS	INITIAL	1,100
\$	PROGRAM	QUTC Activity 2.
\$	LIMITS	10,26K,,
** \$	MASS	A1,A1R,25L (Work file)
** \$	MASS	B1,B1R,25L (Work file)
** \$	TAPE	T1,T1D,,1234,,USER-IN (User's input file)
** \$	TAPE	C1,C1D,,,USER-SORTED (User's output file)
** \$	MASS	S1,S1R,10R (Sort work file)
* \$	MASS	D1,D1R,10R (Work IDS file)
\$	SYSOUT	P1 (Report file)
\$	DATA	.Q
*** IDS	CREATE	FC/D1/,BSSZ/100/,RNG/1,100/
\$	DATA	I*
*** IDS	OPTION	GENERATE/,RANDA/,RNG/1,30000/,
IDS	ETC	CF/2,6/,CF/20,5/,CF/10,2/,FILL/63/
\$	ENDJOB	
***EOF		

* The required file codes are A1 and D1 respectively. The file code A1 on LUD D1S in activity 1 is used as file code D1 on LUD D1R in activity 2. This file must be mass storage.

** The required file codes are as defined in the example. Tape or mass storage are acceptable as file types.

*** The BASESIZE and RANGE for the work I-D-S file may be computed in the following manner using the RANGE from the OPTION directive:

$$((\text{maximum range} - \text{minimum range}) + 1) / 300 = \text{BSSZ}$$

$$((30000 - 1) + 1) / 300 = 100$$

The PAGESIZE for this file must be 320 words and the LINES per page must be 63.

2. Deck Setup for ANAL Option:

1	8	16
\$	IDENT	VTA00,YOUNGMAN,K72
\$	PROGRAM	QUTI Activity 1.
* \$	MASS	A1,D1S,10R
\$	DATA	.Q
*** IDS	CREATE	FC/A1/,BSSZ/100/,RNG/1,100/
\$	DATA	I*
IDS	INITIAL	1,100
\$	PROGRAM	QUTC Activity 2.
\$	LIMITS	10,26K
** \$	MASS	A1,A1R,25L (Work file)
** \$	MASS	B1,B1R,25L (Work file)
* \$	MASS	S1,S1R,10R (Sort work file)
** \$	MASS	D1,D1R,10R (Work I-D-S file)
\$	SYSOUT	P1 (Report file)
\$	DATA	.Q
*** IDS	CREATE	FC/D1/,BSSZ/100/,RNG/1,100/
\$	DATA	I*
*** IDS	OPTION	GENERATE/,ANAL/,RNG/1,30000/,
IDS	ETC	INCR/1/,FILL/63/,MAX/100000/
\$	ENDJOB	
***EOF		

* Same as for RANDA Option.

** Same as for RANDA Option.

*** Same as for RANDA Option.

3. Subroutines Called:

- .QOPEN - opens mass storage device files and builds tables to describe them.
- .QDIR - reads directives.
- .QMEX - writes messages on the execution report.
- .QSFD - advances subfields of the variable field of directive for processing.
- .QCALC - computes a base page number.

		IDS BASE PAGE REPORT		PAGE 001	
PAGE NUMBER	NR OF RECORDS	PAGE NUMBER	NR OF RECORDS	PAGE NUMBER	NR OF RECORDS
1	6	2	2	3	6
4	4	5	4	6	4
7	2	8	12	9	5
10	2	11	6	12	5
13	3	14	5	15	1
16	6	17	3	18	3
19	5	20	6	21	4
22	4	23	5	24	10
25	4	26	3	27	6
28	6	29	8	30	3
31	2	32	6	33	4
34	3	35	5	36	12
37	2	38	4	39	1
40	6	41	2	42	5
43	4	44	2	45	4
46	5	47	8	48	12
49	5	50	3	51	4
52	5	53	4	54	5
55	7	56	7	57	11
58	7	59	5	60	5
61	4	62	4	63	6
64	7	65	5	66	5
67	2	68	7	69	8
70	5	71	3	72	5
73	5	74	3	75	3
76	5	77	10	78	3
79	2	80	12	81	7
82	4	83	4	84	7
85	2	86	2	87	4
88	8	89	1	90	4
91	5	92	6	93	5
94	1	95	6	96	6
97	6	98	6	99	3
100	8				

RANDOMIZED TO STORED ON

8	9
8	10
36	37
36	37
48	49
57	59
77	78

IDS OVERFLOW REPORT
RANDOMIZED TO STORED ON

8	9
24	25
36	37
48	49
48	50
57	59
80	81

PAGE 001
RANDOMIZED TO STORED ON

8	9
24	25
36	37
48	49
57	58
77	78
80	82

Storage Tape Dump/Print Utility Routine (QUTD)

QUTD dumps to tape and/or prints all or selected portions of the appropriate storage devices allocated to the I-D-S data file. The portions of the file to be processed and the output media are specified by input data cards (directives).

Directives

Directive fields begin in column 16 and are separated by commas. One or more ETC cards may be used to continue the fields if they run beyond column 72. Each card to be continued must end with a complete field, followed by a comma.

There are four directives recognized by QUTD.

1	8	16
IDS	DUMP	RNG/P1,P2/ null

The DUMP directive causes pages P1 through P2 to be written on magnetic tape. If the variable field is null, all pages of the file are written on magnetic tape. The file code for the magnetic tape is OT. RNG/P1,P2/ is the only option valid for this directive.

1	8	16
IDS	PRINT	RNG/P1,P2/,..., Print option

The PRINT directive causes P1 through P2 to be written in print format and directed to SYSOUT via file code P*. If RNG is not specified, all pages of the file are written.

Print Options

- NULL Prints nonempty pages and indicates empty pages.
- EMPTY Prints nonempty pages and the page header for each empty page rather than indicating a succession of empty pages only by a first page entry and a last page entry.

TYPES/A,B,C,.../ Prints only the record types specified by A,B,C, etc. (to a maximum of 10 types).

DELETE Produces a file containing reference code, size and record type of all records deleted but still present on the file.

1	8	16
IDS	DPRINT PDUMP	RNG/P1,P2/,.../

The DPRINT/PDUMP directive (either form is acceptable) causes pages P1 through P2 to be written on magnetic tape and to be sent to SYSOUT in print format, via file code P*. Either directive is a combination of the DUMP and PRINT directives. A null variable field causes all pages of the file to be written. All print options listed above are acceptable with either of these directives.

1	8	16
IDS	EOR	(not examined)

The EOR directive forces an end-of-reel condition on the magnetic tape file.

PAGE: XXXXX XX ACTIVE PAGE SIZE: XXXX CH.

WD:	LN:	TYPE:						
XXX	XX	XXXX	OCTAL	OCTAL	OCTAL	OCTAL	OCTAL	BCD
			OCTAL	OCTAL	OCTAL	OCTAL	OCTAL	BCD
			OCTAL	OCTAL	OCTAL	OCTAL	OCTAL	BCD
XXX	XX	XXXX	OCTAL	OCTAL	OCTAL	OCTAL	OCTAL	BCD

PAGE: XXXXX XX ACTIVE PAGE SIZE: XXXX CH. PAGE EMPTY AND ALL INTERVENING PAGES

PAGE XXXXX XX ACTIVE PAGE SIZE: XXXX CH. PAGE EMPTY

Tape Format

The data sent to the output tape file is written as variable length, logical records using the GEFRC subroutine PUT. The file is in standard system format with the exception of block size which is 1602 words. The Page Image record format is:

<u>Word</u>	<u>Contents</u>
0	Accounting Record Header. The number of data words in the record is specified in bits 0-17. The record type, octal 000013, is contained in bits 18-35.
1	Checksum.
2	SNUMB in bits 0-29. Ignore character (octal 17) in bits 30-35.
3	Date as MMDDYY.
4	Start time in hours and thousandths of hours as HH.TTT.
5	Record type in bits 0-11 as 10. Bits 12-35 are presently unused and are zero.
6	This word is presently unused and is zero.
7	First six characters of user identification.
8	Second six characters of user identification.
9-n	Active page image.

Execution Report

An execution report is produced as part of the user output. It describes, in chronological order, the functions performed as specified in the directives. In addition, error conditions are included to advise the user of exception conditions.

Operation

The following deck setups can be used to execute QUTD from the software library.

1. Example for temporary files.

1	8	16
\$	IDENT	
\$	PROGRAM	QUTD
\$	LIMITS	OPTIONS
\$	MASS	A1,X1R,15R (required file code)
\$	TAPE	OT,X2S,,,,DUMP-FILE (required file code)
\$	TAPE	DE,X3S,,,,DELETE-FILE (required file code)
\$	DATA	.Q
IDS	CREATE	FC/A1/,BSSZ/480/,RNG/1,120/,LPP/63/
\$	DATA	I*
IDS	PDUMP	DELETE/
\$	ENDJOB	
***EOF		

- a. Pages 1 through 120 will be written to tape (file code OT).
- b. All nonempty pages will be printed on P* and all empty pages will be indicated with a beginning and ending page number.
- c. All records logically but not physically deleted from the file will be written to tape (file code DE) and flagged on the printed report.

2. Example for permanent files.

1	8	16
\$	IDENT	
\$	PROGRAM	QUTD
\$	LIMITS	OPTIONS
\$	USERID	IDSF0URYQUAD\$DBASE
\$	PRMFL	TF, R/W, R, IDSF0URYQUAD\$DBASE/QUAD01
\$	PRMFL	TG, R/W, R, IDSF0URYQUAD\$DBASE/QUAD02
\$	TAPE	QT, X2S, , , , DUMP-FILE
\$	DATA	I*
IDS	DUMP	RNG/1, 120/
IDS	DPRINT	EMPTY/, TYPES/100, 101, 102/
\$	ENDJOB	
***EOF		

This deck setup will result in the following:

- a. Pages 1 through 120 (file code TF) will be written to tape (file code OT).
- b. File code TG, in its entirety, will be written to tape.
- c. All page headers and all record types 100, 101 and 102 on file code TG will be printed.

QUTI

Page Initialize Utility Routine (QUTI)

QUTI initializes all or selected portions of the appropriate storage devices allocated to the I-D-S data file with the page headers and creates or updates the inventory records. The portions of the file to be processed are specified by an input data card (directive). The attributes of the file are acknowledged during the initialization process.

Directives

There are two directives recognized by .QUTI.

1	8	16
IDS	INITIAL	P1,P2

The initial directive causes pages P1 through P2 to be initialized with their page headers and the inventory records to be created as required.

1	8	16
IDS	HEADER	P1,P2

The header directive causes pages P1 through P2 to be initialized with their page headers and the inventory records to be updated as required. This requires that the portion of the file must have been previously initialized by the initial directive. This directive allows a portion of the file to be purged and the inventory to be reset.

Directive Restrictions

1. The argument P2 must be greater than or equal to the argument P1.
2. Directives are examined to ensure that columns 8-13 contain a legal directive code as described. Directives in error are written on the execution report followed by appropriate comments.

Execution Report

An execution report is produced as part of the user output. It describes, in chronological order, the functions performed as specified in the directives. In addition, error conditions are included to advise the user of exception conditions.

Operation

1. Deck setup.

The following deck setup will initialize a permanent I-D-S data file.

1	8	16
\$	SNUMB	QUTI
\$	IDENT	IDS00,DATABASEMGR
\$	USERID	IDSF0URYQUAD\$DATABASE
\$	PROGRAM	QUTI
\$	PRMFL	A1,R/W,R,IDSF0URYQUAD/QUAD01
IDS	INITIAL	1,120
\$	ENDJOB	
***EOF		

The following deck setup can be used to initialize a temporary I-D-S data file.

1	8	16
\$	SNUMB	QUTI
\$	IDENT	IDS00,DATABASEMGR,TEMP FILE
\$	PROGRAM	QUTI
\$	"file"	or A1,X1S,13R (A1 is the required file code)
\$	DATA	.Q
IDS	CREATE	FC/A1/,BSSZ/480/,RNG/1,120/,PGSZ/192/, LPP/32/,INV/25/
\$	DATA	I*
IDS	INITIAL	1,120
\$	ENDJOB	
***EOF		

2. Subroutines called.

.QDIR - reads directives.

.QMEX - writes messages on the execution report.

.QMWD - moves blocks of words from one location in memory to another.

.QPSP - supplies a tallied I/O list for pages to be read from the mass storage device(s).

.QSFD - advances subfields of the variable field of directive for processing.

.QDIRC - closes the directive file.

.QDIRP - establishes the file code (I*) for directives.

.QOPEN - opens the mass storage device file(s) and builds the tables that describe them.

.QRTAB - verifies that the requested pages are allocated and builds the tables, by device, for the required page ranges.

.QSICT - points indirectly to the mass storage device file descriptions.

.QTAB1 - contains table of FROM page ranges.

.QTAB2 - contains table of TO page ranges.

.QTAB3 - contains the number of entries, minus one, in .QTAB1/:QTAB2. This count is in bits 0-17. Bits 18-35 are not examined.

.QWAIT - insures that all outstanding I/O on the mass storage device is completed.

.QBCD - converts binary to BCD and replaces leading zeros with blanks.

.QMCH - moves blocks of characters from one location in memory to another.

.QINVL - updates inventory.

.QWRIT - performs buffered writing to the mass storage device.

.QPHI - generates the page headers.

.QCLOS - closes the files and generates the I/O statistic report.


.QMAP1 - calculates the relative sector.

Journal Tape Dump Utility Program (QUTJ)

QUTJ dumps selected portions of tapes in the standard I-D-S journal format. This includes tapes created by master mode or slave mode journalization, and tapes produced by either QUTU, QUTP, or QUTS.

Directive

One directive is recognized by the QUTJ program.



The SYSTEM directive causes only record types 3 and 4 (SLVBGN and SLVEND) to be printed on the report. All other record types are ignored.

Printer Format

The record types recognized by QUTJ are printed in the format shown below.

Record Type	Column 1	Column 2	Column 3	Column 4	Column 5	Column 6	Column 7	Column 8	Column 9	Column 10
Slave Begin	Logical Record Number		SLVBGN	AA-SSSSS	Date	Time	Record Type	Sequence Word	12 Character user ID	Blank
Slave End	Logical Record Number		SLVEND	AA-SSSSS	Date	Time	Record Type		12 character user ID	Blank
BEFORE Image	Logical Record Number		BEFORE	AA-SSSSS	Date	Time	Record Type	Sequence Word	12 character user ID	Page Number
AFTER Image	Logical Record Number		AFTER	AA-SSSSS	Date	Time	Record Type	Sequence Word	12 character user	Page Number
QUTU Image	Logical Record Number		QUTU	AA-SSSSS	Date	Time	Record Type	Sequence Word	12 character user ID	Page Number

Column Description

Column 2 - Two asterisks appear in this column if the checksum of this record is in error.

Column 5 - DATE is displayed in the form of MM-DD-YY.

Column 6 - TIME is displayed as HH.TTT, hours and thousandths of hours.

Column 8 - This word is the abort code for SLVEND records. A code of 00 is used for end of activity and end of job.

The SEQUENCE word is zero for all record types except BEFORE and AFTER. BEFORE page image records are incremented by 1, starting with 1 in bits 18-35. AFTER page image records are decremented by 1, starting with -1.

Column 10 - The PAGE NUMBER is the first 18 bits of the first word of the page image followed by the line number.

Execution Report

QUTJ writes the printed output on the execution report via SYSOUT. The input tape label is the first line of the report.

Operation

The following deck setup can be used to execute QUTJ.

1	8	16
\$	IDENT	
\$	PROGRAM	QUTJ
\$	LIMITS	Options
\$	TAPE	IN,Options (IN is required file code)
\$	ENDJOB	
***EOF		

Sample Output

The following page illustrates the output format produced by QUTJ; the input tape was a master mode journal tape.

IDS UTILITY ROUTINE - IOUTJ - VERSION 080168,

3	SLVBGN	1-TST03	10-01-68	11,037	030	0	IDSF0URYQUAD		
4	BEFORE	1-TST03	10-01-68	11,037	050	1	IDSF0URYQUAD	22	0
5	BEFORE	1-TST03	10-01-68	11,037	050	2	IDSF0URYQUAD	382	0
6	BEFORE	1-TST03	10-01-68	11,037	050	3	IDSF0URYQUAD	20	0
7	BEFORE	1-TST03	10-01-68	11,037	050	4	IDSF0URYQUAD	380	0
8	BEFORE	1-TST03	10-01-68	11,037	050	5	IDSF0URYQUAD	112	0
9	BEFORE	1-TST03	10-01-68	11,037	050	6	IDSF0URYQUAD	472	0
10	BEFORE	1-TST03	10-01-68	11,037	050	7	IDSF0URYQUAD	55	0
11	BEFORE	1-TST03	10-01-68	11,037	050	8	IDSF0URYQUAD	415	0
12	BEFORE	1-TST03	10-01-68	11,037	050	9	IDSF0URYQUAD	65	0
13	BEFORE	1-TST03	10-01-68	11,037	050	10	IDSF0URYQUAD	425	0
14	BEFORE	1-TST03	10-01-68	11,037	050	11	IDSF0URYQUAD	33	0
15	BEFORE	1-TST03	10-01-68	11,037	050	12	IDSF0URYQUAD	393	0
16	BEFORE	1-TST03	10-01-68	11,037	050	13	IDSF0URYQUAD	86	0
17	BEFORE	1-TST03	10-01-68	11,037	050	14	IDSF0URYQUAD	446	0
18	BEFORE	1-TST03	10-01-68	11,037	050	15	IDSF0URYQUAD	115	0
19	BEFORE	1-TST03	10-01-68	11,037	050	16	IDSF0URYQUAD	475	0
20	AFTER	1-TST03	10-01-68	11,037	060	262142	IDSF0URYQUAD	22	0
21	BEFORE	1-TST03	10-01-68	11,037	050	17	IDSF0URYQUAD	70	0
22	AFTER	1-TST03	10-01-68	11,037	060	262141	IDSF0URYQUAD	382	0
23	BEFORE	1-TST03	10-01-68	11,037	050	18	IDSF0URYQUAD	430	0
24	AFTER	1-TST03	10-01-68	11,037	060	262140	IDSF0URYQUAD	20	0
25	BEFORE	1-TST03	10-01-68	11,037	050	19	IDSF0URYQUAD	68	0
26	AFTER	1-TST03	10-01-68	11,037	060	262139	IDSF0URYQUAD	380	0
27	BEFORE	1-TST03	10-01-68	11,037	050	20	IDSF0URYQUAD	428	0
28	AFTER	1-TST03	10-01-68	11,037	060	262138	IDSF0URYQUAD	112	0
29	BEFORE	1-TST03	10-01-68	11,037	050	21	IDSF0URYQUAD	40	0
30	AFTER	1-TST03	10-01-68	11,037	060	262137	IDSF0URYQUAD	472	0
31	BEFORE	1-TST03	10-01-68	11,037	050	22	IDSF0URYQUAD	400	0
32	AFTER	1-TST03	10-01-68	11,037	060	262136	IDSF0URYQUAD	55	0
33	BEFORE	1-TST03	10-01-68	11,037	050	23	IDSF0URYQUAD	16	0
34	AFTER	1-TST03	10-01-68	11,037	060	262135	IDSF0URYQUAD	415	0
35	BEFORE	1-TST03	10-01-68	11,037	050	24	IDSF0URYQUAD	376	0
36	AFTER	1-TST03	10-01-68	11,037	060	262134	IDSF0URYQUAD	65	0
37	BEFORE	1-TST03	10-01-68	11,037	050	25	IDSF0URYQUAD	111	0
38	AFTER	1-TST03	10-01-68	11,037	060	262133	IDSF0URYQUAD	425	0
39	BEFORE	1-TST03	10-01-68	11,037	050	26	IDSF0URYQUAD	471	0
40	AFTER	1-TST03	10-01-68	11,037	060	262132	IDSF0URYQUAD	33	0
41	BEFORE	1-TST03	10-01-68	11,037	050	27	IDSF0URYQUAD	1	0
42	AFTER	1-TST03	10-01-68	11,037	060	262131	IDSF0URYQUAD	393	0
43	BEFORE	1-TST03	10-01-68	11,037	050	28	IDSF0URYQUAD	361	0
44	AFTER	1-TST03	10-01-68	11,037	060	262130	IDSF0URYQUAD	86	0
45	BEFORE	1-TST03	10-01-68	11,037	050	29	IDSF0URYQUAD	81	0
46	SLVBGN	1-TST3C	10-01-68	11,038	030	0	IDSF0URYQUAD		
47	AFTER	1-TST03	10-01-68	11,037	060	262129	IDSF0URYQUAD	446	0
48	BEFORE	1-TST03	10-01-68	11,037	050	30	IDSF0URYQUAD	441	0
49	BEFORE	1-TST3C	10-01-68	11,038	050	1	IDSF0URYQUAD	142	0
50	AFTER	1-TST03	10-01-68	11,037	060	262128	IDSF0URYQUAD	115	0
51	BEFORE	1-TST03	10-01-68	11,037	050	31	IDSF0URYQUAD	22	0
52	BEFORE	1-TST3C	10-01-68	11,038	050	2	IDSF0URYQUAD	262	0

Data Base Load/Print Utility Routine (QUTL)

QUTL loads and/or prints all or selected I-D-S pages from an input file. The input file may be:

- Dump File created by QUTD
- Selected File created by QUTS
- System Statistical Collection File or User Journal File (JX)

DIRECTIVES

The QUTL utility is controlled through the following directive:

1	8	16
IDS	OPTION ETC ETC	Function/Input Descriptor/, Descriptor options/, PRINT OPTIONS/

Directive fields being in column 16, they are terminated by a slash (/) and are separated by commas. One or more ETC cards may be used to continue the fields. A directive card to be continued must end with a complete field, followed by a comma.

Operation

The operation of the utility varies depending upon the type of input file. The utility is written in a modular (overlay) manner such that only the coding needed to accomplish the desired function is engaged.

There are three INPUT DESCRIPTOR options recognized by the utility:

DTAPE
STAPE
JTAPE

The directive options applicable for each type of INPUT DESCRIPTOR and resulting operation are described as though three unique utilities actually exist.

The Printer Format and Tape Formats are common to the three modes of operation.

DTAPE

DTAPE - Input Descriptor

The use of DTAPE as the Input Descriptor indicates that the input file contains data produced by the I-D-S utility QUTD.

DIRECTIVE OPTIONS

FUNCTION

LOAD Causes specified pages to be written on the mass storage device.

PRINT Causes specified pages to be written in print format and directed to SYSOUT via file code P*.

LPRINT These options (either form is acceptable) cause the specified pages to be written on the mass storage device and to be sent to SYSOUT in print format via file code P*. Either directive is a combination of the PRINT and LOAD functions.

PLOAD

EOR Forces a unit switch on the input magnetic tape file.

RNG/P1,P2/ Specifies the page range to be reloaded and/or printed. If no range is present the entire range of all subfiles allocated is assumed. The argument P2 must be greater than or equal to P1.

PRINT OPTIONS

EMPTY Prints non-empty pages and the page header for each empty page rather than indicating a succession of empty pages only by a first page entry and last page entry.

TYPES/A,B,C,.. / Prints only the record types specified by A,B,C,.. (to a maximum of 10 types).

DELETE Produces a file containing reference code, size and record type of all records logically but not physically deleted from the file. The required file code is DE.

Rev. August 1971

Directive Examples:

1	8	16
IDS	OPTION	DTAPE/,LOAD/

This requests reloading of all pages for all files allocated to the activity.

1	8	16
IDS	OPTION	DTAPE/,PLOAD/

This requests reloading of all pages for all files allocated to the activity and printing of all nonempty pages with all empty pages being indicated with a first page and last page entry.

1	8	16
IDS	OPTION	DTAPE/,PLOAD/,EMPTY/,
	ETC	TYPES/100,200/,RNG/18500,25000/,
	ETC	DELETE/

This requests reloading of all pages for the specified range, printing of all page headers and any records of the specified types. A file of all deleted records will also be produced.

Execution Report

An execution report is produced as a part of the output. It describes in chronological order, the functions performed as specified in the directive. In addition, error conditions are included to advise the user of exception conditions.

The input and output files are double buffered to obtain maximum throughput. The input file must contain consecutive pages for the files allocated or the PAGE-RANGE specified on the directive card. If nonconsecutive pages are encountered during execution, an error comment is written on the execution report and the program is aborted with a D2 reason code.

Inventory records will be created for the file or PAGE-RANGE re-loaded if applicable.

The minimum core requirement for this activity is 16K.

Operation

The following deck setup can be used to execute QUTL from the software library.

1. Example for temporary files.

1	8	16
\$	IDENT	(options)
\$	PROGRAM	QUTL
\$	LIMITS	(options) (minimum 16K)
\$	MASS	A1,X1R,15R
\$	TAPE	IN,X2S,,1234,,DUMP-FILE (Required File code)
\$	TAPE	DE,X3S,,,,DELETE-FILE (Required File code)
\$	DATA	.Q
IDS	CREATE	FC/A1/,BSSZ/480/,RNG/1,120/
\$	DATA	I*
IDS	OPTION	DTAPE/,PLOAD/,RNG/1,120/,DELETE/
\$	ENDJOB	

This deck setup will result in the following:

- Pages 1 through 120 will be written to the mass storage device.
- All non-empty pages will be printed on P* and all empty pages will be indicated with a beginning and ending page number.
- All records logically but not physically deleted from the data base will be written to tape (file code DE) and flagged on the printed report.

2. Example for permanent files:

1	8	16
\$	IDENT	(options)
\$	PROGRAM	QUTL
\$	LIMITS	(options)
\$	USERID	IDSF0URYQUAD\$DBASE
\$	PRMFL	TF,R/W,R,IDSF0URYQUAD\$DBASE/QUAD01
\$	PRMFL	TG,R/W,R,IDSF0URYQUAD\$DBASE/QUAD02
\$	PRMFL	TH,R/Q,R,IDSF0URYQUAD\$DBASE/QUAD03
\$	PRMFL	TI,R/Q,R,IDSF0URYQUAD\$DBASE/QUAD04
\$	TAPE	IN,X2S,,1234,,DUMP-TAPE (Required File code)
\$	DATA	I*
IDS	OPTION	DTAPE/,PLOAD/,EMPTY/,RNG/121,240/

This deck setup will result in the following:

- a. Pages 121 through 240 will be written on the mass storage device.
- b. All non-empty pages and page headers for all empty pages will be printed on P*.

STAPE

STAPE - Input Descriptor

The use of STAPE as the Input Descriptor indicates that the input file contains data as produced by the I-D-S utility QUTS.

Input File

The input file is standard system formats with the exception of block size, which is 1602 words. The data on the file must have been written as output by the I-D-S utility QUTS; therefore it must consist of either the first BEFORE or last AFTER for each page supplied as input and only one image for each page will be present.

DIRECTIVE OPTIONS

FUNCTION

LOAD	Causes specified pages to be written on the mass storage device.
PRINT	Causes specified pages to be written in print format and directed to SYSOUT via file code P*.
LPRINT PLOAD	These options (either form is acceptable) cause specified pages to be written on the mass storage device and to be sent to SYSOUT in print format via file code P*. Either directive is a combination of the PRINT and LOAD functions.
EOR	Forces a unit switch on the input magnetic tape file.

DESCRIPTOR OPTIONS

RNG/P1,P2/	Specifies the page range to be reloaded and/or printed. If no range is present, the entire range of all subfiles allocated is assumed. The argument P2 must be greater than or equal to P1.
------------	---

Rev. August 1971

PRINT OPTIONS

TYPES/A,B,C,.../ Prints only the record types specified by A,B,C,... (to a maximum of 10 types).

DELETE Produces a file containing reference code, size and record type of all records logically but not physically deleted from the file. The required file code is DE.

DIRECTIVE EXAMPLES

1	8	16
IDS	OPTION	STAPE/,LOAD/

This requests reloading of all pages found on the input tape for all files allocated.

1	8	16
IDS	OPTION	STAPE/,PLOAD/,RNG/27500,35000/

This requests reloading and printing of all pages found for the specified range.

Execution

An execution report is produced as a part of the output. It describes in chronological order, the functions performed as specified in the directive. In addition error messages are included to advise the user of exception conditions.

Since pages are non-consecutive on this type load and each page must be processed based on the page number found in the record, the input is double buffered and the output is accomplished from the input buffer.

Minimum core requirement for this type load is 14K.

Inventory records will be updated for each page reloaded if applicable.

Operation

The following deck setup can be used to execute QUTL from the software library.

1. Example for temporary files.

1	8	16
\$	IDENT	(options)
\$	PROGRAM	QUTL
\$	LIMITS	(options)
\$	MASS	A1,X1R,15R (required File code)
\$	TAPE	IN,X2S,,1234,,DUMP-FILE (Required File code)
\$	DATA	.Q
IDS	CREATE	FC/A1/,BSSZ/480/,RNG/1,120/
\$	DATA	I*
IDS	OPTION	STAPE/,LOAD/
\$	ENDJOB	

This causes reloading all pages found on the input tape for all files allocated.

2. Example for permanent files:

1	8	16
\$	IDENT	(options)
\$	PROGRAM	QUTL
\$	LIMITS	(options) (minimum 14K)
\$	USERID	IDSF0URYQUAD\$DBASE
\$	PRMFL	TF,R/W,R,IDSF0URYQUAD\$DBASE/QUAD01
\$	PRMFL	TG,R/W,R,IDSF0URYQUAD\$DBASE/QUAD02
\$	PRMFL	TH,R/Q,R,IDSF0URYQUAD\$DBASE/QUAD03
\$	PRMFL	TI,R/W,R,IDSF0URYQUAD\$DBASE/QUAD04
\$	TAPE	IN,X2S,,1234,,SELECT-FILE
\$	DATA	I*
IDS	OPTION	STAPE/,PLOAD/,RNG/100,200/
\$	ENDJOB	

This requests reloading and printing of all pages found for the specified range.

JTAPE - Input Descriptor

The use of JTAPE as the Input Descriptor indicates that the input file contains data of the System Statistical Collection Tape or a User Journal File (JX

Input File

The input file may be one or more reels of the master mode System Statistical Collection tape or User Journal File. The file must be in system standard format with the exception of block size, which is 1602 words.

DIRECTIVE OPTIONS

FUNCTION

LOAD	Causes specified pages to be written on the mass storage device.
PRINT	Causes specified pages to be written in print format and directed to SYSOUT via file code P*.
LPRINT PLOAD	These options (either form is acceptable) cause specified pages to be written on the mass storage device and to be sent to SYSOUT in print format via file code P*. Either directive is a combination of the PRINT and LOAD functions.
EOR	Forces a unit switch on the input magnetic tape file.
NORWD	Suppresses rewinding of the input tape at the end of each directive.

DESCRIPTOR OPTIONS

RNG/P1,P2/ Specifies the page range to be loaded and/or printed. If no range is present, the entire range of all subfiles allocated is assumed. The argument P2 must be greater than or equal to P1.

SNUMB/XXXXX/,ACT/A1,A2/ This selects page images for the specified SNUMB starting with activity A1 through activity A2. If only activity A1 is specified, that is the only activity to be selected. If no activity is specified, all page images for the SNUMB are looked at.

FILE/FILENAME/ This selects page images associated with the specified filename. If this option is used, it must be the only directive to be processed.

PAGE/1,2,3.../ This option provides selection of specific pages. When this option is used, a FILE/FILENAME/ must be specified. A maximum of 10 pages may be specified on one directive.

DATE/YMMDD/ This option, in conjunction with FILENAME or SNUMB, accomplishes selection of records with a date equal to or greater than the one specified.

DATE/YMMDD/,TIME/HHTTT/ This provides selection of records with a date and time equal to or greater than that specified.

AFTER Specifies either BEFORE or AFTER images are to be loaded. If neither option is specified, BEFORE is assumed.

BEFORE

PRINT OPTIONS

TYPES/A,B,C,.../ Prints only the record types specified by A,B,C,... (to a maximum of 10 types).

DELETE Produces a file containing reference code, size and record type of all records logically but not physically deleted from the file. The required file code is DE.

Rev. August 1971

DIRECTIVE EXAMPLES

```
1      8      16
-----
|IDS  |OPTION |JTape/,PLOAD/,SNUMB/12345/,
|     |ETC    |ACT/05/
```

This loads and prints the first BEFORE images found on the journal tape for SNUMB 12345, activity 5. All nonempty pages and page headers for all empty pages will be printed on P*.

```
1      8      16
-----
|IDS  |OPTION |JTape/,PLOAD/,FILE/IDSF0URYQUAD/,
|     |ETC    |DATE/700608/,TIME/13.058/,AFTER/
```

This loads all AFTER page images found on the journal tape for SNUMB 12345, activity 5. All nonempty pages and page headers for all empty pages will be printed on P*.

```
1      8      16
-----
|IDS  |OPTION |JTape/,PLOAD/,FILE/IDSF0URYQUAD/,
|     |ETC    |DATE/700608/,TIME/13.058/,AFTER/
```

This loads all AFTER page images found on the journal tape for file IDSF0URYQUAD with a date and time equal to or greater than the one specified. All nonempty pages will be printed and all empty pages will be indicated.

Execution

An execution report is produced as part of the user output. It describes, in chronological order, the functions performed as specified in the directives. In addition, error conditions are included to advise the user of execution conditions.

Considerations

This type load utilizes a tape which will probably contain multiple before and after images for each page; therefore, when loading before images a control must be maintained to ensure that only the first before image of each page is written to the data base. This is accomplished through utilization of a page-flag "bit-buffer".

In order to allow dynamic construction of the bit-buffer at execution time, the amount of core required for the bit buffer is based on the accumulated ranges of all subfiles allocated to the job and the accumulated ranges specified on the directive cards. It is the user's responsibility to provide enough core to accommodate this requirement.

The minimum core requirement for this version of QUTL (excluding the bit-buffer) is 15K. A formula for calculating the bit buffer size per subfile or range is described below:

$$(\text{MAX. RANGE} - \text{MIN. RANGE} + 1) * \text{PAGES-PER-PAGE} / 36$$

= Number of words of core required per subfile or range

Total core required would be the sum of all subfile or range computations plus 15K.

EXAMPLE

A program aborts leaving two subfiles to be recovered. One subfile has a page-range of 1 - 10000 while the second subfile contains pages 10001 - 20000 for a total of 20,000 pages. If no range is specified on the QUTL directives, enough core (556 words) must be allocated to construct a bit buffer large enough to map 2000 pages. However, suppose the determination can be made, based on knowledge of the aborted program, that only pages 9000 - 12000 were affected, this range may then be specified on the directive and only enough core (84 words) to map 3000 pages would be required.

Multiple directives may be processed with one execution of QUTL; however, they will be processed in the order in which they appear in the job stream. Consider the following example:

1	8	16
IDS	OPTION	JTAPE/,LOAD/,SNUMB/12345/,ACT/2/
IDS	OPTION	JTAPE/,LOAD/,SNUMB/23456/,ACT/2,5/

All before images for SNUMB/12345/,ACT/2/ will be looked at on the first pass of the accounting tape. The bit buffer will be checked to ensure only the first before image of each page is written to the data base.

The Journal tape will be rewound and the second directive, SNUMB/23456/ activities two through five will be processed. The page flag bits set by the first directive will be checked while processing the second directive, so that should each job have changes the same pages in the data base, only the first before image written by the first directive is restored. At completion of the QUTL activity, the data base would be restored to a point prior to any changes made by either job.

The user may suppress rewinding of the accounting tape between directives by specifying NORWD on the directive cards. This option should be used when the jobs to be recovered were run in sequence rather than concurrently.

Operation

The following deck setup can be used to execute QUTL from the software library:

Example for permanent files:

1	8	16
\$	IDENT	(options)
\$	PROGRAM	QUTL
\$	LIMITS	(options) (minimum 15K + bit buffer)
\$	USERID	IDSFOURYQUAD\$DBASE
\$	PRMFL	TF,R/W,R,IDSFOURYQUAD\$DBASE/QUAD01
\$	PRMFL	TG,RECOVERY/R/W,R,IDSFOURYQUAD\$DBASE/QUAD02
\$	TAPE	IN,X2S,,1234,,JOURNAL-TAPE (Required File Code)
\$	DATA	I*
IDS	OPTION	JTAPE/,LOAD/,SNUMB/56789/,ACT/01,05/,NORWD/
IDS	OPTION	JTAPE/,LOAD/SNUMB/567890/,ACT/02/
\$	ENDJOB	

This deck setup will result in the following:

1. The first before image of each page associated with SNUMB 56789 activity 1 through activity 5 found on the journal tape will be written to the I-D-S DATA BASE IDSFOURYQUAD.
2. The NORWD directive prevents rewinding the journal tape prior to processing the next directive.
3. The first before image of each page associated with SNUMB 567890 activity 2, not reloaded when processing the first directive, will be reloaded on file IDSFOURYQUAD.

Printer Format

The format of pages selected for printer output is shown below:

PAGE: XXXXX XX ACTIVE PAGE SIZE: XXXX CH.

WD:	LN:	TYPE:					
XXX	XX	XXXX	OCTAL	OCTAL	OCTAL	OCTAL	BCD
			OCTAL	OCTAL	OCTAL	OCTAL	BCD
			OCTAL	OCTAL	OCTAL	OCTAL	BCD
XX	XX	XXXX	OCTAL	OCTAL	OCTAL	OCTAL	BCD

PAGE: XXXXX XX ACTIVE PAGE SIZE: XXXX CH. PAGE EMPTY
 AND ALL INTERVENING PAGES

PAGE XXXXX XX ACTIVE PAGE SIZE: XXXX CH. PAGE EMPTY

Input File Format

The data read from the input tape file consists of variable length, logical records. The file is in standard system format with the exception of block size which is 1602 words. The record format is:

Word Contents

- 0 Accounting Record Header. The number of data words in the record is specified in bits 0-17. The record type, octal 000013, is contained in bits 18-35.
- 1 Checksum.
- 2 SNUMB in bits 0-29. Ignore character (octal 17) in bits 30-35.
- 3 Date as MMDDYY.
- 4 Start time in hours and thousandths of hours as HH.TTT.
- 5 Record type in bits 0-11 as 10. Bits 12-35 are presently unused and are zero.
- 6 This word is presently unused and is zero.
- 7 First six characters of user identification.

- 8 Second six characters of user identification.
- 9-n Active page image.

Delete File FORMAT

The optional output file of records logically but not physically deleted from the data base is in standard system format. The record format is:

<u>Word</u>	<u>Contents</u>
0	Reference code. Page number in bits 12 - 29. Line number in bits 30 - 35.
1	Record type.
2	Record size in characters.

QUTP

Journal Record Selector Utility Program (QUTP)

QUTP selects records from an I-D-S journal tape according to user-supplied criteria and writes them on an output tape.

Directives

Two types of control cards are recognized by QUTP: SELECT and ETC. The first card must be a SELECT; the second is optional.

1	8	16
IDS	SELECT	f1,f2,f3

where f1 must be AA/SSSSS. This field specifies the Activity and SNUMB of the corresponding Slave Begin record which must be found to initiate interrogation of this criterion. The AA/SSSSS format must be one or two digits for the activity number, slash, and five digits for the SNUMB.

f2 must be AA/SSSSS. This field specifies the Activity and SNUMB (which must be the same SNUMB as in f1) of the corresponding Slave End record which must be found to terminate interrogation of this criterion.

f3 is either B, A, or null. This field specifies the type of record to be selected for interrogation. If this field is null, B is implied. If ETC cards are present, this field is ignored. B stands for Before and A stands for After.

Two SELECT card examples are:

1	8	16
IDS	SELECT	1/53607,1/53607,B
IDS	SELECT	12/88802,13/88802,A

The ETC card is optional. It is used to specify that only BEFORE or AFTER records for a given page range are to be selected for output. The format of this directive is:

1	8	16
	ETC	f1/f2/f3,f1/f2/f3, ...etc...

where f1 is B or A meaning BEFORE or AFTER.

f2 is the lower limit of a page range.

f3 is the upper limit of a page range.

NOTE: $1 \leq f2 \leq f3 \leq 262,143$

Several page range specifications may be placed on one ETC card, but each triplet must be separated from the next one by a comma. A slash must separate each element of a triplet. If several page range specifications are placed on one ETC card, the last data character must be followed by a blank, and the blank must appear prior to or in column 72. Several ETC cards may follow a SELECT card as long as the maximum of 8 triplets per SELECT is not exceeded.

If ETC card(s) follow a SELECT, then field f3 of the SELECT card is ignored since this option is specific for each page range.

Two ETC card examples are:

1	8	16
	ETC	B/129/352,A/26243/53409
	ETC	A/1/100,A/10/20

Directive Restrictions

A maximum of 50 directives is allowed. Following each SELECT directive, there may be a maximum of eight page range specifications.

Tape Format

The input data for this program can be one or more reels of master mode journal tape information. The file must be in standard system format with the exception of block size, which is 1602 words.

Records are written on the output file in standard system format with the exception of block size. Two types of records may appear on the output tape: BEFORE and AFTER. Their format is:

<u>Word</u>	<u>Contents</u>
0	Accounting Record Header. The number of data words in the record is specified in bits 0-17. The record type, octal 000013, is contained in bits 18-35.
1	Checksum.
2	SNUMB in bits 0-29. Ignore character (octal 17) in bits 30-35.
3	Date as MMDDYY.
4	Start time in hours and thousandths of hours as HH.TTT.
5	Record type in bits 0-11 as 10. Bits 12-35 are presently unused and are zero.
6	Lines per page for this page image (bits 1-17).
7	First six characters of user identification.
8	Second six characters of user identification.
9-n	Active page image.

Execution Report

A detailed execution report is printed by QUTP. The report is divided into two parts. Part 1 is a listing of the directives and part two is the summary report.

Operation

1. Deck setup.

The following deck setup can be used to execute QUTP.

1	8	16
\$	IDENT	
\$	PROGRAM	QUTP
\$	LIMITS	Options
\$	TAPE	IN,Options (IN is required file code for the input tape)
\$	TAPE	OT,Options (OT is required file code for the output tape)
		Directives
\$	ENDJOB	
***EOF		

2. QUTP performs three distinct functions to select the specified records.

PROCESSING DIRECTIVES. The directives are read as data from the input file I*. Each card is checked for errors in both content and format. If errors are present, an error comment is written with the card image on the execution report; and a switch is set so that a D2 abort occurs when all directives have been scanned, but before processing of the input tape is initiated. When scanning is complete and no error has occurred, a sequence number is assigned to the directive and printed on the execution report. The criterion is then stored in memory. Since all criteria are resident in core, the user need not order them.

RECORD INTERROGATION. As each input record is read from tape, its record type is examined to determine how it should be handled.

The SLVBGN and SLVEND records are used to initiate and terminate testing on a criterion. For example, if a criterion specifies all BEFORE records within a specific SLVBGN-SLVEND, the criterion is turned on when the matching SLVBGN is encountered to interrogate BEFORE records and output those that match. Correspondingly, the matching SLVEND turns off the criterion. This technique allows inactive criteria to be quickly recognized and bypassed.

The BEFORE and AFTER records are matched against specific criteria. If the tests are successful, the records are written.

SUMMARY REPORT. After all criteria are satisfied or an end-of-file is reached on the input file, a summary report is produced on the execution report. Specific criteria of each directive and the number of output records for the directive are shown.

QUTR

Execution Information Report Program (QUTR)

QUTR selects type B information records from an I-D-S journal file, sorts the records, and produces an execution information report.

Input Tape Format

The input file is standard system format except for a maximum block size of 1602 words.

Operation

1. Subroutine .QSTB.

For each SNUMB-activity that engages subroutine .QSTB, type B statistics are collected on the I-D-S journal file as a type 09 record. These are the records used as input by QUTR. Thus, to provide this input, the following loader control card must be included in the job stack for the activity:

1	8	16
\$	USE	.QSTB

Type B information is then accumulated by .QSTB for each primary entry subroutine (that is, each subroutine called by the object program).

2. Deck Setup.

The following deck setup shows the appropriate control cards for (1) collecting type B statistics on the journal file and (2) executing QUTR.

	1	8	16
①	\$	IDENT	
	\$	USERID	
②	\$	USE	.QSTB
	\$	OBJECT	
		.	
③		.	
	\$	DKEND	
	\$	EXECUTE	
	\$	PRMFL	
④	\$	TAPE	JX,X1S,,,,I-D-S JOURNAL
		.	
⑤		.	
		.	
⑥	\$	PROGRAM	QUTR
⑦	\$	SYSOUT	P1
⑧	\$	TAPE	A1,X1R
⑨	\$	TAPE	B1,X2R,,,99999
⑩	\$	NTAPE	S1,T,2
	\$	ENDJOB	
		***EOR	

Notes:

- ① Beginning of activity.
- ② Provides for collecting type B information in type 09 journal records.
- ③ Object deck.
- ④ User-created journal file.
- ⑤ Other user files (and end of activity).
- ⑥ Beginning of second activity (for producing a type B statistics report).
- ⑦ P1 is required output file code.
- ⑧ A1 is required input journal tape file code. (Note that this is the journal file created in first activity.)
- ⑨ B1 is required file code for sort work file (scratch tape).
- ⑩ S1 is required file code for the first of two collation tapes needed by GE-600 Line Sort/Merge.

Sample Output

A sample output for QUTR is shown on the following page. The circled callouts are keyed to the following notes:

- ① Alter number (from GMAP codes) of the call to the subroutine
- ② Function (similar to I-D-S statement)
- ③ Record type
- ④ Record type of chain master followed by record type of a detail
- ⑤ Number of times the call was executed
- ⑥ Number of times the subroutine was executed without requiring I/O
- ⑦ Total number of reads for execution of the subroutine
- ⑧ Total number of writes for execution of the subroutine

ALTER	FUNCTION		CALLS	ZERO I/O	READS	WRITES
135	STORE	RECORD TYPE 990	1	0	1	0
166	RETRIEVE	RECORD TYPE 990	1	1	0	0
169	RETRIEVE NEXT OF CHAIN	990 4	21	3	17	18
179	DELETE	RECORD TYPE 4	20	2	0	18
184	RETRIEVE NEXT OF CHAIN	990 50	20	19	0	6
215	RETRIEVE DIRECT		19	0	19	19
217	RETRIEVE NEXT OF CHAIN	1000 4	19	19	0	0
282	STORE	RECORD TYPE 1	5	0	6	4
291	STORE	RECORD TYPE 2	5	0	6	5
300	STORE	RECORD TYPE 3	5	1	4	4
309	STORE	RECORD TYPE 4	5	0	6	5
410	STORE	RECORD TYPE 50	20	20	0	0
①	②	③	⑤	⑥	⑦	⑧

Selected Record Sort Utility Program (QUTS)

QUTS sorts and merges records selected from an I-D-S journal tape. The sorted and merged records may be used to reload the user data base when recovery to a previous file status is desired.

Input Tape Format

The input file is standard system format with the exception of block size, which is 1602 words. The data on the input file must have been written as output by the I-D-S Journal Record Selector (QUTP); therefore, it must consist of BEFORE and AFTER record types only.

Output Tape Format

The output files are standard system format with the exception of block size, which is 1602 words. The data on the output files consists of the first BEFORE or last AFTER record for each page supplied as input.

Execution Report

QUTS produces an execution report as part of the user output. This report describes in chronological order the functions performed during the execution. In addition, error messages are included to advise the user of exception conditions.

Operation

1. Deck setup.

The following deck setup describes the appropriate control cards for executing QUTS using tapes. Disc sort may also be used instead of tapes.

1	8	16
\$	IDENT	
\$	PROGRAM	QUTS
\$	LIMITS	10,24K
\$	TAPE	IN,Options
\$	TAPE	OT,Options
\$	TAPE	OU,Options
\$	NTAPE	S1,Options,3
\$	ENDJOB	
***EOF		

A limit card is required. The minimum is 19K, however for sort to run with greater efficiency a limit of at least 24K is suggested.

IN is the required input file code.

OT is the required file code for the first output file.

OU is the required file code for the second output file. (This file need not be present if the input to QUTS consists only of records from a single file; that is, one file name.)

SI is the required file code for the first of three collation tapes required by GE-600 Line Sort/Merge. A minimum of three collation tapes is required.

2. QUTS consists of input coding and output coding elements coupled to the standard GE-600 Line Sort/Merge. The individual functions performed are described below.

INPUT CODING. The input coding element reads and preprocesses all input records from the input file:

A sequence number is placed in bits 0-17 of the seventh word of all BEFORE and AFTER records. For each BEFORE record, the sequence number is ascending and ranges in value from 1 to 777777(8). For each AFTER record, the sequence number is descending and ranges in value from 777777(8) to 1. This sequence number preserves the chronological order of the input records in cases where start times may be identical for two different activities.

Each input record is tested to ensure that only record types 05 and 06 comprise the input. Invalid records are dumped in octal format on the execution report accompanied by an appropriate error comment. An indicator is set when invalid records are encountered so that the program terminates with a D2 code after all input records are processed.

SORT CODING. The standard GE-600 Line Sort/Merge is used to arrange input records in the desired order for output. The fields used for sorting and their sequence are:

<u>Sequence</u>	<u>Field Size</u>	<u>Field Description</u>
1st (major key)	2 words	File-name
2nd	18 bits	Page number
3rd	10 bits	Page
4th	2 characters	Record type
5th	1 word	Sequence number
6th	24 bits	CALC chain next

OUTPUT CODING. Two files are available for output in this coding element. A control break on file-name results in closing the first output file and opening the second output file. The specific functions performed in the output coding element are:

- a. The sequence number in bits 0-17 of the sixth word is set to zero.
- b. The page number of the current record is compared to the page number of the previous record and, if they are the same, the current record is not written to the output file.

QUTT

QUTT Not Available

QUTT Tape Conversion Utility Program is no longer available.

File Utility Program (QUTU)

QUTU performs the following I-D-S utility functions, depending upon the directives chosen:

- File initialize (INIT directive): establishes page headers and initializes inventory.
- File print/graph (PRINT directive): prints requested pages, record types, and inventory; graphs space and lines used for requested pages; and prints a record type usage report.
- File movement (WRITE directive): moves requested pages from one file to another. (This is a DUMP/LOAD facility.)
- File reformat (WRITE directive): changes page size and/or lines per page of requested pages while performing file movement to a tape or random file.

Directives

Directive fields begin in column 16 and are separated by commas. One or more ETC cards may be used to continue the fields if they run beyond column 72. Each card to be continued must end with a complete field, followed by a comma. A directive card followed by one ETC card is shown below.

1	8	16
IDS	INIT	FC/XX/,RNG/A,B/,RNG/C,D/,
	ETC	RNG/E,F/,RNG/G,H/,...

Formats for the program input directives are shown below, arranged by program function. Directive restrictions are listed at the conclusion of the format explanations.

Function 1: File Initialize (random files only; if file is tape, directive is ignored)

1	8	16
IDS	INIT	FC/XX/,RNG/A,B/,RNG/C,D/,...

where FC/XX/ is the file to be initialized. This field must be present.

For permanent random files: XX is as defined on the \$PRMFL card.

For temporary random files: XX is A1 for the first file, A2 for the second, etc.

RNG/A,B/ is a page range to be initialized.

If no range field is present, the entire range of the file is initialized. A must be less than or equal to B, and B must be less than or equal to 262,144.

RNG/C,D/, if present, is a second page range to be initialized. A maximum of 8 ranges will be considered on one directive.

Example for permanent files:

```
1      8      16
-----
$      SNUMB
$      IDENT
$      PROGRAM QUTU
$      LIMITS  10,24K
$      USERID  IDSF0URYQUAD$DBASE
$      PRMFL   TF,R/W,R,IDSF0URYQUAD/QUAD01
$      PRMFL   TG,R/W,R,IDSF0URYQUAD/QUAD02
IDS    INIT    FC/TF/,RNG/1,120/
IDS    INIT    FC/TG/,RNG/121,240/
```

Example for temporary files:

```
1      8      16
-----
$      SNUMB
$      IDENT
$      PROGRAM QUTU
$      LIMITS  10,24K
$      MASS    A1,X1S,11R
$      MASS    A2,X2S,22R
$      DATA    .Q
IDS    CREATE  FC/A1/,BSSZ/480/,RNG/1,120/,LPP/63/
IDS    CREATE  FC/A2/,BSSZ/480/,RNG/121,240/,LPP/32/
$      DATA    I*
IDS    INIT    FC/A1/
IDS    INIT    FC/A2/
```

Function 2: File Print/Graph

1	8	16
IDS	PRINT	FC/XX/,RNG/A,B/,RNG/C,D/,...., print option

where FC/XX/ is the file to be printed; and
 RNG/A,B/ are the ranges of that file to be
 RNG/C,D/ printed.

Example for permanent files:

1	8	16
\$	SNUMB	
\$	IDENT	
\$	PROGRAM	QUTU
\$	LIMITS	10,24K
\$	USERID	IDSFOURYQUAD\$DBASE
\$	PRMFL	TF,R/W,R,IDSFOURYQUAD/QUAD01
\$	PRMFL	TG,R/W,R,IDSFOURYQUAD/QUAD02
\$	DATA	I*
IDS	PRINT	FC/TF/,RNG/1,10/,PAGES
IDS	PRINT	FC/TG/,EMPTY

Example for temporary files:

1	8	16
\$	SNUMB	
\$	IDENT	
\$	PROGRAM	QUTU
\$	LIMITS	10,24K
\$	MASS	A1,X1R,11R
\$	MASS	A2,X2R,22R
\$	DATA	.Q
IDS	CREATE	FC/A1/,BSSZ/480/,RNG/1,120/,LPP/63/
IDS	CREATE	FC/A2/,BSSZ/480/,RNG/121,240/,LPP/32/
\$	DATA	I*
IDS	PRINT	FC/A1/
IDS	PRINT	FC/A2/,RNG/121,150/,GRAPH

The print options and their resulting actions are as follows (each option generates a different report code to prevent report "shuffling" on SYSOUT; only one option is allowed per PRINT directive but a maximum of 8 PRINT directives is allowed):

- NULL Results in the same action as PAGES (see below).
- EMPTY Prints nonempty pages and prints a line for each empty page rather than indicating a succession of empty pages only by a first-page entry and a last-page entry. An inventory printout is included.

GRAPH Prints a graph showing, for each page, the percent of space used and number of lines used in the page.

GRAPH/N/ Prints a graph showing, for each N pages and/or pagettes, the average percent of space used and average number of lines used per page. Note: Use caution in interpreting averages that include two different page sizes.

INV Prints inventory only.

PAGES Prints nonempty pages, indicates empty pages, and prints inventory.

RECORD Prints a report of record types usage within each of the specified ranges.

Because of the large buffer space required, a record type usage report cannot be generated for both the input and output file over the same range. If two reports are requested, the second request is ignored.

TYPES/A,B,C,.../ Prints only the record types specified by A,B,C, etc. (to a maximum of 8 types).

Function 3: File Movement/Reformat

1	8	16
IDS	WRITE	FC/XX/,RNG/A,B/,RNG/C,D/,..., ONFC/YY/,PAGE/SZ,LPP/

where FC/XX/ is the file to be read; and
 RNG/A,B/
 RNG/C,D/ are the ranges of that file.

ONFC/YY/ is the file to be written. For temporary random files, YY must be A1,A2, etc.

PAGE/SZ,LPP/ indicates the reformatting parameters for a tape output file. (This field is not used if the output file is random. Page format on random output files is defined by the file attributes.)

SZ is page size in words.
 LPP is lines per page.

If PAGE is present, both parameters must be present. If the output file is tape and the PAGE field is not present, the output format will be the same as the input format.

Example for permanent files:

1	8	16
\$	SNUMB	
\$	IDENT	
\$	USERID	IDSF0URYQUAD\$DBASE
\$	PROGRAM	QUTU
\$	LIMITS	10,24K
\$	PRMFL	TF,R/W,R,IDSF0URYQUAD/QUAD01
\$	PRMFL	TG,R/W,R,IDSF0URYQUAD/QUAD02
\$	TAPE	DT,X1S
\$	DATA	I*
IDS	WRITE	FC/TF/,ONFC/DT/
IDS	WRITE	FC/TG/,ONFC/DT/
		And the reloading of the files from
		the dump tape
\$	PROGRAM	QUTU
\$	LIMITS	10,24K
\$	PRMFL	TF,R/W,R,IDSF0URYQUAD/QUAD01
\$	PRMFL	TG,R/W,R,IDSF0URYQUAD/QUAD02
\$	TAPE	DT,X1D
\$	DATA	I*
IDS	WRITE	FC/DT/,ONFC/TF/
IDS	WRITE	FC/DT/,ONFC/TG/

Example of initialize, execute, dump, and reload for temporary files:

1	8	16
\$	SNUMB	
\$	IDENT	
\$	PROGRAM	QUTU
\$	LIMITS	10,24K
\$	MASS	A1,X1S,11R
\$	MASS	A2,X2S,22R
\$	DATA	.Q
IDS	CREATE	FC/A1/,BSSZ/480/,RNG/1,120/,LPP/63/
IDS	CREATE	FC/A2/,BSSZ/480/,RNG/121,240/,LPP/32/
\$	DATA	I*
IDS	INIT	FC/A1/
IDS	INIT	FC/A2/

User's Program to be executed with its required control cards

\$	PROGRAM	QUTU
\$	LIMITS	10,24K
\$	TAPE	DT,X6S
** \$	MASS	A1,X2S,22R
\$	DATA	.Q
** IDS	CREATE	FC/A1/,BSSZ/480/,RNG/121,240/,LPP/32/
\$	DATA	I*
** IDS	WRITE	FC/A1/,RNG/121,240/,ONFC/DT/

And the reloading of that file from the dump tape

\$	PROGRAM	QUTU
\$	LIMITS	10,24K
** \$	MASS	A1,X2R,22R
\$	TAPE	DT,X6R
\$	DATA	.Q
** IDS	CREATE	FC/A1/,BSSZ/480/,RNG/121,240/,LPP/32/
\$	DATA	I*
** IDS	WRITE	FC/DT/,RNG/121,240/,ONFC/A1/

**NOTE: FC/A1/ is used to reference the file which in the first activity was created and defined as FC/A2/.

Directive Restrictions

Besides the restrictions included in the discussions of the various directives, the following apply:

1. A maximum of 8 INIT, 8 PRINT, and 8 WRITE directives will be processed.

2. A maximum of 8 RNG fields will be considered on any one directive.
3. A maximum of 8 record types will be considered on any one PRINT directive TYPES field.
4. When a range is defined on a directive, the input file must contain that entire range with pages in sequence.
5. If no RNG field is present on a PRINT or WRITE directive, any pages found on the input file that can be written to SYSOUT (with PRINT) or the output file (with WRITE) will be handled.
6. Only SDL-1 (and later) dump format tapes will be read and written.
7. 24,000 words of core storage are necessary for program execution.
8. Any output tape files must contain ranges which do not require writing on one tape, then on another and then on the first again. For example, the following is legal:

<u>Ranges</u>	<u>Tapes</u>
1 - 100	} 1
200 - 1000	
1001 - 1100	} 2
1700 - 1800	

The following is illegal:

<u>Ranges</u>	<u>Tapes</u>
1 - 100	} 1
200 - 1000	
101 - 150	2

9. Since subroutine OPEN is used, all rules defined by OPEN for overlapping ranges, etc., hold for this utility, if a random file is involved.
10. Only SDL-2 (and later) sorted journal tapes may be processed.

Printer Format

The printer output formats for the PRINT options are described below and illustrated in the "Sample Outputs" section. The circled numerals refer to the corresponding callouts on the sample outputs (Figures 38-41).

PAGES option (see Figure 38):

- ① PAGE xxxxxx xxxxxx: page number in octal, then decimal.
- ② xx LINES xx USED: total number of lines existing on this page, number of these used; both in decimal.
- ③ SIZE, CHAR; USED xxxx, AVAIL xxxx: number of characters used, number still available; both in decimal. (Sum of these is size in number of characters.)
- ④ BEGINNING LINE NUMBER xx: beginning line number of page.
- ⑤ CALC CHAIN NEXT xxxxxxxx: contents of the CALC chain NEXT field (octal).
- ⑥ LN xx xx: line number in octal, then in decimal.
- ⑦ TP xxxx: data record type in decimal.
- ⑧ SZ xxxx: record size in characters (decimal).
- ⑨ W+xxx: number of words from beginning of the page.
Cxx : beginning character in the word W+xxx.
- ⑩ xxxxxxxxxxx: octal control word, equivalent to ⑥, ⑦, and ⑧.
- ⑪ Contents of line defined in ⑥, ⑦, ⑧, and ⑩.
- ⑫ Octal data.
- ⑬ BCD data, equivalent to octal data on same printed line.
- ⑭ Same information as in ⑥, ⑦, ⑧, ⑨ and ⑩ for next line.

Notes:

1. If a page is empty, only the following appears:

PAGE xxxxxx xxxxxx PAGE EMPTY

If two or more succeeding pages are empty, the following appears after the line shown above:

THRU

PAGE xxxxxx xxxxxx PAGE EMPTY

2. Selecting the PAGES option also causes an inventory for the range (as shown for the INV option) to be printed by SYSOUT.

EMPTY option:

The output for this option is the same as for PAGES (including an inventory), except that for each empty page - that is, succeeding pages as well as single ones - the following appears:

PAGE xxxxxx xxxxxx PAGE EMPTY

TYPES option:

The output for this option is the same as for PAGES, except for the following:

1. No inventory is included.
2. Only the selected record types are printed.
3. If a page contains records but none are of the requested types, the following appears:

PAGE xxxxxx xxxxxx NO REQUESTED RECORD TYPES

INV option (see Figure 39):

- ① PAGE
xxxxxx xxxxxx : Page number in octal, then decimal
- ② LINE
xx xx : Line number in octal, then decimal
- ③ #AVAIL
xxx : Percent of space available, shown in either of two ways:
 - a. When the space used in the page is less than the percentage specified in the user's inventory update request, this condition is indicated by a #AVAIL of xx (where xx is 100# minus the inventory update request). Thus, this indication shows only that the inventory update request percentage has not been exceeded.
 - b. When the space used in the page is greater than the percentage specified in the user's inventory update request, this condition is indicated by a #AVAIL xx (where xx is the actual percentage of total space that is still available).
- ④ THRU : Indicates that, for the pages from the page and line preceding this word through the page and line following, the AVAIL is the same.

RECORD option (see Figure 40):

- ① RECORD TYPE
xxx : I-D-S record type.
- ② SIZE
xxx : Record size in characters. (The size is flagged by an asterisk if it is inconsistent.)
- ③ NUMBER
xxxx : Number of occurrences of record type within specified range.
- ④ NUMBER DELETED
xxxx : Number of this record type logically deleted within the specified range.
- ⑤ LOW PAGE
xxxx : Page number of first occurrence of record type within the specified range.
- ⑥ HIGH PAGE
xxxx : Page number of last occurrence of record type within the specified range.
- ⑦ RANGE
xxxx - xxxx : Specified range for report.

GRAPH and GRAPH/N/ options (see Figure 41):

- ① Page numbers.
- ② Scale for percent of space used (0 - 100).
- ③ Scale for number of lines used (0 - 63).
- ④ # character, showing percent of space used.
- ⑤ # character, showing number of lines used.
- ⑥ X character, used when # and # values coincide.

Notes:

1. For GRAPH/N/, the numbers of the pages at interval N appear in the column at 1. The symbols opposite these numbers represent averages for the percent of space used and number of lines used within the interval.
2. Multiple entries for the same page number can occur if GRAPH (rather than GRAPH/N/) is specified when pagettes are included.

Tape Format

The data sent to the output tape file is written as variable length, logical records using the GEFRC subroutine PUT. The file is in standard system format with the exception of block size which is 1602 words. The Page Image record format is:

<u>Word</u>	<u>Contents</u>
0	Accounting Record Header. The number of data words in the record is specified in bits 0-17. The record type, octal 000013, is contained in bits 18-35.
1	Checksum.
2	SNUMB in bits 0-29. Ignore character (octal 17) in bits 30-35.
3	Date as MMDDYY.
4	Start time in hours and thousandths of hours as HH.TTT.
5	Record type in bits 0-11 as 10. Bits 12-35 are presently unused and are zero.
6	UTL in bits 0-17 to indicate utility tape rather than journal tape. Bits 18-35 unused.
7	First six characters of user identification.
8	Second six characters of user identification.
9-n	Active page image.

Execution Report

An execution report is produced as part of the user output. It includes open and close reports for any random files used (see examples 1 and 2, respectively, in Chapter 6, "I-D-S Execution Report") and a list of the directives used in order of execution. (See Figure 42 in "Sample Outputs" section for example of directive list.)

The report may also include any of the following error messages (all but no. 9 describe conditions causing a program abort):

1. FILE CODE XX RANGE REQUESTED NOT IN FILE

A range has been defined by a directive for a random file (XX) which is inconsistent with the range defined in the file attributes.

2. FILE CODE XX CANNOT HANDLE REDUNDANT RANGE

Range had been defined by a directive for this file (XX) with an intervening range requested by another file (see "Directive Restrictions," no. 9).

3. CANNOT HANDLE MORE THAN 8 FILES

More than 8 directives of any one type (INIT, PRINT, WRITE) have been input.

4. PREVIOUS CARD FATAL ERROR

The preceding card contains an error -- no file code, missing comma, or missing slash.

5. PREVIOUS CARD TOO MANY RANGES

More than eight ranges are defined on the preceding directive.

6. PREVIOUS CARD TOO MANY RECORD TYPES

More than eight record types are defined on the preceding directive.

7. FILE CODE XX INPUT IS NOT SEQUENTIAL

The file (XX) does not contain all of the pages defined by a following range field.

8. FCXX ON FCXX PAGE TOO SMALL

In reformatting, the output page size is not large enough to contain the lines to be written in the page.

9. FILE CODE XX CHECKSUM ERROR

A checksum error has been found on file XX. This is noted but the program does not abort. (See also "Directive Restrictions," no. 7.)

10. FILE CODE XX DATA READ NOT PAGE OR PAGETTE

The file XX does not contain page images. This is the result of a bad tape or bad random file.

Operation

The following deck setup can be used to execute QUTU.

1	8	16
\$	IDENT	
\$	USERID	
\$	PROGRAM	QUTU
\$	LIMITS	10,24000
\$	PRMFL	
\$	DISC	
\$	DRUM	or Options
\$	MASS	
\$	TAPE	Options
	.	
	.	
	.	
	.	
	.	
\$	ENDJOB	
***EOF		

Sample Outputs

Figures 38-42 on the following pages show the various sample outputs mentioned in the "Printer Format" and "Execution Report" sections.

```

    ①      ②      ③      ④      ⑤
PAGE 000003 000003, 32 LINES 32 USED SIZE,CHAR| USED 1415,AVAIL 905 BEGINNING LINE NUMBER 1 CALC CHAIN NEXT 00000301
LN 01 01,TP 0001,SZ 0203,W+ 3,C 4 0100010313 000003100000 000006061103 020031244325 511462202631 00380000669320IDLERS FI
    ⑥      ⑦      ⑧      ⑨      ⑩      ⑪
    254324202020 202020202020 202020010745 031103060400 00380000669320IDLERS FI
    450100020302 030366000503 244500040105 004500014545 00380000669320IDLERS FI
    212145450005 030000000000 060527516227 433121622120 00380000669320IDLERS FI
    202045010607 642020202045 200304076420 202020452045 00380000669320IDLERS FI
    204520204520 202020000001 254520202020 202020202020 00380000669320IDLERS FI
    202020202020 202020202020 202020202020 204520202020 00380000669320IDLERS FI
    202020202020 202020204520 202020202020 202020202020 00380000669320IDLERS FI
    202100000302 000500050300 000303 000500050300 000303 000500050300 000303
LN 02 02,TP 0026,SZ 0014,W+ 37,C 3 0200320016 000500050300 000303
    ⑫      ⑬
    00380000669320IDLERS FI
    ELD 17N393640
    N1023233W053DNO4150N01NN
    AANN0530000065GRSGLIASA
    N167U N 347U N N
    N N 001EN
    N
    A0032
    050530033
  
```

Figure 38. Sample PAGES Option Output

PAGE	LINE	XAVAIL	PAGE	LINE	XAVAIL	PAGE	LINE	XAVAIL
000001	000001	01 01 0	000001	000001	41 33 >75 THRU	000003	000003	00 00 >75
000003	000003	01 01 0	000003	000003	41 33 >75	000004	000004	01 01 0
000004	000004	41 33 >75 THRU	000007	000007	00 00 >75	000007	000007	01 01 0
000010	000008	00 00 0	000010	000008	01 01 >75 THRU	000015	000013	00 00 >75
000015	000013	01 01 0	000015	000013	41 33 >75 THRU	000017	000015	00 00 >75
000017	000015	01 01 0	000017	000015	41 33 >75	000020	000016	01 01 0
000021	000017	40 32 02	000021	000017	41 33 >75 THRU	000025	000021	00 00 >75

① ② ③b ③a ④

Figure 39. Sample INV Option Output

USAGE	RECORD TYPE	SIZE	NUMBER	NUMBER DELETED	LOW PAGE	HIGH PAGE	RANGE	1 - 50
	2	139	377	0	1	50		

① ② ③ ④ ⑤ ⑥ ⑦

Figure 40. Sample RECORD Option Output




Figure 41. Sample GRAPH Option Output

41632 01 08-12-69 14.778

DIRECTIVE:	PRINT	FC/T2/,RNG/1,50/
DIRECTIVE:	PRINT	FC/T2/,RNG/1,50/,GRAPH
DIRECTIVE:	PRINT	FC/T2/,RNG/1,50/,RECORD

Figure 42. Sample QUTU Execution Report Directive List

Directive Processor and Service Subroutine (.QDIR)

.QDIR is a collection of ten different subroutines designed to provide common functions for I-D-S utility programs and subroutines. Each different function is defined by its SYMDEF name:

.QDIRF

This symbol identifies word -4 of the file control block for the data file. Bits 24-35 of this word contain the file code for the data file. If the user wishes to use his own file code, then he must initialize these bits prior to any call to .QDIR or .QSFD. The assumed directive file code is I*.

.QDIR

This subroutine opens the file for directives and reads the directive into memory. Columns 8-13 are left justified and stored in a cell pointed to by the user in the calling sequence. This value is also returned to the user in the A-register.

As each directive is read from the data file, columns 1 through 84 (14 words) are moved to a working buffer. The literal words DIRECTIVE: precede this buffer. After the move is completed, the .QMEX subroutine is called to print the literal and the card image on the execution report. A slew to the next line is given with each line of printing.

In addition, a tally word is initialized to point to column 16 of the directive for scanning the variable field through calls to the .QSFD entry point.

ETC cards are also read by this subroutine.

The calling sequence is:

1	8	16
	CALL	.QDIR(ARG1)ALT1

where:

ARG1 = The location for the contents of columns 8-13 of the directive.

ALT1 = The location for an end of file exit.

.QSFD

This entry point is called to scan the variable field of a directive starting in column 16. Each call to this entry point will scan a maximum of 12 characters, if a delimiter is not encountered. The valid delimiters are comma, blank, and slash.

The n characters are returned left justified with trailing blanks in the AQ-register as well as being returned to the three cells pointed to by the user in the calling sequence. The delimiter character is not returned.

The third word pointed to by the calling sequence will contain three values:

Bits 0-17: The number of characters in the subfield.


Bits 18-23: The delimiter character found.

Bits 24-35: The value required for a right shift of the AQ-register in order to right justify the subfield.

It should be noted that if the value in 0-17 is zero, then the value in bits 24-35 will be 72.

If more than 12 characters are present in the subfield then only the first 12 characters are returned to the user. The tally word for the scan is advanced through the next delimiter. The character count in bits 0-17 of the user's argument will contain the total number of characters in the subfield.

The calling sequence is:



where:

ARG1 = The address of three consecutive cells for return information. The first two cells will contain the subfield, left justified, with trailing blanks. The third word will contain the three values described above.


.QDIRC

This subroutine closes the directive file. If only one file code is used with .QDIR, the user need not call this subroutine.

.QBCD

This subroutine converts a number from binary to BCD and replaces leading zeros with blanks. The number to be converted may not be larger than 999,999(10). If the binary number is zero, it will be converted to five blanks and a zero.


The calling sequence is:



.QCLR

This subroutine clears n words to a preset value. The argument list specifies the number of words to be cleared, the address of the area to be cleared, and a pointer to the value to be stored in the area.

The calling sequence is:




.QCSM

This subroutine calculates the checksum of a specified number of words starting at a given location. If the starting location is given as A, then the word at A+1 will be skipped (not added into the checksum).

The calculated checksum is returned to the user in the A-register.

The calling sequence is:



where:

ARG1 = The number of words to be checksummed.


ARG2 = Address of word 0 of data to be checksummed.

Note: If the number of words to be checksummed is 0, 1, or 2, then the first word of data is returned to the user as the checksum.

.QMCH

This subroutine moves n characters from address A, starting character position A1, to address B, starting character position B1.

The calling sequence is:




Starting character positions must be from 0 through 5.

.QMEX

This subroutine is called to write messages on the execution report. Messages must be less than or equal to 22 words in length. If a length of zero is given, a line of blanks will be written and the specified slew code will be appended to the end of the line. Messages greater than 22 words in length will be truncated to 22 words.

The calling sequence is:




where:

ARG1 = The number of words in the message

MSG = The address of the message

SLEW = The number of lines to be slewed after printing. (See the GEFRC routines, IOEDIT and PRINT, for slew code rules.)

If a fourth argument is present (the value in the argument has no bearing) in the call, then a 'Top of Page' will be issued prior to printing the line requested by the caller. After the top of page is issued, a heading line is printed with the SNUMB, activity number and date followed by a double space. Then the caller's line is printed. If the caller wants just a top of page without any information printed, he should write the call as:




The zero word count in the above printed call will cause a line of blanks to be printed with the slew code specified.

.QMWD

This subroutine moves n words from address A to address B.


The calling sequence is:



.QPBK

This subroutine is called to journalize a page. The page will be sent to the user's journal file if it is present. If no user's file is present, then the page will be journalized to the I-D-S system journal.

The calling sequence is:



where:

FCB = The LOCSYM of the file control block for the journal file.

PTR = The address of a word which points to the origin of the data to be journalized. This origin is the location of the accounting header word which precedes the page.

The record size for journalization is obtained from bits 0-17 of the accounting header word.

It is the user's responsibility to checksum the record and store the checksum in the record prior to calling .QPBK. The file control block defined by the user for the journal file must specify only one buffer.

Trace and Print Record, Debug, and Utility Subroutine (.QSTC)

The .QSTC subroutine generates a trace entry for all calls to I-D-S primary subroutines (except for .QOPEN and .QCLOSE). In addition, each time a call is issued to one of the following primary subroutines, .QSTC prints the current record:

.QSTOR	.QCHN
.QGET	.QHEAD
.QGETC	.QMDFY
.QGETD	.QMOVE
.QGETE	.QDELETE

The trace data and the record to be printed are directed to P* unless otherwise specified by the user. The user can direct this output to his own file, if desired.

Trace data and print record entries are generated on P* or a users' file for all I-D-S record types, for each I-D-S primary subroutine (those listed above), and for the entire page range of the I-D-S file unless otherwise specified by the user. The user has the option of selecting:

1. Which primary subroutine(s) should be traced.
2. Which record(s) should be printed.
3. Up to five different page ranges within the I-D-S file.
4. Which record types (up to a maximum of 50) should be traced or printed.

The .QSTC subroutine is controlled through the following I-D-S Directive.

1	8	16
IDS	OPTION	DEBUG OPTIONS, FILE OPTION,
	ETC	DIRECTIVE/OPTION/,
	ETC	DIRECTIVE/OPTION/,
	ETC	...

DEBUG OPTIONS

- PRTREC This Debug Option causes the contents of the current record to be printed after the completion of an I-D-S call. Sample output is shown in Figure 43.
- TRACE This Debug Option causes a trace data line to be generated each time one of the previously listed I-D-S primary subroutines is called. Sample output is shown in Figure 43.

Note: Either PRTREC or TRACE or both PRTREC and TRACE must be specified.

FILE OPTION

- ONFC/xx/ The inclusion of ONFC/xx/ causes the trace data and/or the output generated as a result of PRTREC to be directed to the users' file with the file code xx. If ONFC/xx/ is not included, the output is directed to p*.

DIRECTIVES

- NULL Provides the full capabilities of the option specified.
- ALL Provides the full capabilities of the option specified.
- DO Only the specified options will be performed.
- DONTDO Processing of the specified options is inhibited.

OPTIONS

- TYPES/nnn,...,nnn/

Depending on the specified directive, this option allows or inhibits the tracing and/or printing of specified record types. A maximum of 50 different record types can be specified.

- VERBS/xxx,...,xxx/

Depending on the specified directive, this option allows or inhibits the tracing and/or printing of the current record as a result of a call to an I-D-S function. The allowable verbs are:

RETRIEVE
RETRIEVEEACH (or EACH)
RETRIEVENEXT (or NEXT)
RETRIEVECURRENT (or CURRENT)
RETRIEVEDIRECT (or DIRECT)
HEAD
STORE
MODIFY
MOVE
DELETE

- RNG/lB,lE,...,5B,5E/

Depending on the specified directive, this option allows or inhibits the tracing and/or printing of current I-D-S records that are within a specified page range. lB...5B specify beginning page numbers; lE...5E specify ending page numbers. A maximum of five different page ranges may be specified.

RESTRICTIONS

- For the same option, specification of a DONTDO directive overrides the specification of a DO directive.
- Both the DONTDO and the DO directives apply to both the TRACE and PRTREC functions.
- Imbedded blanks cause the processing of an OPTION card to be terminated.

EXAMPLES

1	8	16
IDS	OPTION	TRACE

This causes a trace data line to be generated on P* each time one of the previously listed I-D-S primary subroutines is called.

1	8	16
IDS	OPTION	PRTREC,ALL

This causes a print record entry on P* for all I-D-S record types and for each I-D-S primary subroutine (those previously listed) for the entire range of the I-D-S file.

1	8	16
IDS	OPTION ETC	TRACE,DO/TYPES/001,942/, DONTDO/VERBS/MOVE,STORE/

This causes the tracing of only the record types 001 and 942 for the entire range of the I-D-S file and inhibits tracing of the I-D-S verbs MOVE and STORE for those record types. The output is directed to P*.

1	8	16
IDS	OPTION ETC ETC ETC	TRACE,PRTREC,ONFC/AB/, DO/RNG/001,005,009,010/, ALL/TYPES/,DO/VERBS/, RETRIEVE,MODIFY,DELETE/

This causes the tracing and printing of all record types referred to by the verbs RETRIEVE, MODIFY, and DELETE that are within the page ranges 001 to 005 and 009 to 010. The trace data and print record are directed to the user's file with the code AB.

1	8	16
\$	DATA	.Q
IDS	OPTION	PRTREC,DO/TYPES/941/,
	ETC	DO/VERBS/RETRIEVE/,
	ETC	DO/RNG/016,900/

This example causes all record type 941 (name and address record) to be printed each time a RETRIEVE verb accesses a record type 941 between pages 016 and 900. The output is directed to P*.

DECK SETUPS

The following deck setup may be used to execute on an I-D-S PRMFL.

1	8	16
\$	IDENT	IDSTST,PAT
\$	USERID	IDSFOURYQUAD\$DATABASE
	OBJECT	PROGRAM
\$	USE	.QSTC
\$	EXECUTE	
\$	PRMFL	A1,R/W,R,IDSFOURYQUAD/QUAD1
\$	DATA	.Q
IDS	OPTION	PRTREC,TRACE,ALL
\$	ENDJOB	
***EOF		

The following deck setup may be used to execute a program using a temporary I-D-S file.

1	8	16
\$	IDENT	IDSTST,PAT
	OBJECT	PROGRAM
\$	USE	.QSTC
\$	EXECUTE	
\$	DISC	A1,X1R,9R
\$	TAPE	B1,X2D
\$	DATA	.Q
IDS	CREATE	FC/A1/,BSSZ/100/,RNG/1,100/
IDS	OPTION	TRACE,ONFC/B1/,DONTDO/RNG/1,50/
\$	ENDJOB	
***EOF		

Note: To provide the TRACE and PRTREC options the following LOADER control card must be included in the job stack for the activity.

1	8	16
\$	USE	.QSTC

USER ENTRY POINT

A users' entry point has been provided which enables the printing of the current I-D-S record. This entry is available to the user regardless of whether PRTREC or TRACE has been specified.

```
1      8      16
|-----|
|        |SYMREF |QSTA4
|        |CALL   |QSTA4(ARG);
|        |
```

where ARG is a one word working storage location to be used as a line count.

STANDARD ERROR OPTION

If TRACE is specified by the user and an I-D-S error occurs, an error message is generated to the output file code specified by the user. Refer to Figure 43 for example.

SUBROUTINE RESTRICTIONS

1. If the user entry point (QSTA4) is called, all output generated is directed to P*.
2. If any field within an I-D-S record exceeds 84 characters, only the first 84 will be printed by the PRTREC module. If a field is modified, the PRTREC module shows the result of the entire field.
3. If the modify verb is called to modify a record with more than 100 fields, modify flags appear on the first 100 fields modified; all others are not flagged.
4. If this subroutine is used with a user program which has not been compiled using the .QNAMS macro, the field and record name areas of all output will contain unpredictable data. This condition will also cause faulty printing in some cases.

To include this macro, the user must include the following code within the Procedure Division after the first ENTER IDS. statement.

```
14      22
|-----|
|ENTER  |GMAP .
|.QNAMS |
|ENTER  |COBOL .
```

5. If ONFC/XX/ file option is used and the specified file is not defined as having variable-length records or if file is not assigned as a printed file, the results are unpredictable.

6. If ONFC/XX/ file option is used and the specified file is not opened before the first I-D-S statement, all output is directed to P*.

OUTPUT DESCRIPTION

Figure 43 shows typical TRACE and PRTREC output. A description of all generated data fields follows:

- ① Complete trace entry
 - ② Complete PRTREC entry showing fields names and field content
 - ③ TRACE heading
 - ④ GMAP alter number within program where I-D-S call was issued
 - ⑤ Current type of I-D-S operation
 - ⑥ Current record type
 - ⑦ Page and line number of current I-D-S record
 - ⑧ PRTREC header shows type of I-D-S operation, record name, and page and line number of current I-D-S record
 - ⑨ Field-name of record
 - ⑩ Field contents
 - ⑪ Control field - this field shows field usage, allowable contents are:
 - RDM - Randomize field key
 - STA - Sorted ascending field key
 - STD - Sorted descending field key
 - MAT - Match key or synonym field
 - ⑫ Data Type:
 - AN - Alphanumeric
 - A - Alpha
 - N - Numeric
 - SN - Signed Numeric
 - SFX - Single precision, fixed point
 - SFP - Single precision, floating point
 - DFX - Double precision, fixed point
 - DFP - Double precision, floating point
- Note: All field contents that are not BCD will be printed in OCTAL.
- ⑬ I-D-S error entry with error code
 - ⑭ An (*) will appear by each field name which had its contents changed by the user calling the I-D-S modify routine

```

66536 05 09-29-69      21.173  (4)
***** IDS-TRACE * ALTER NO.- 293  (5)
(3)          DATREC          MAT CALDAT          (6)          (7)
STOR DATDET          120/ 2  0992          9998          STA ACTDAT          CODDAT          (1)
***** IDS-TRACE * ALTER NO.- 293  (5)
(8)          DATREC          MAT CALDAT          (6)          (7)
STOR DATDET          120/ 3  0992          9999          STA ACTDAT          CODDAT          (1)
***** IDS-TRACE * ALTER NO.- 263  (5)
XXXXXXXX AN IDS ERROR HAS OCCURED, ERROR CODE - D01 } (13)
          DATREC          MAT CALDAT          (6)          (7)
STOR DATDET          120/ 3  0992          9999          STA ACTDAT          CODDAT          (1)
***** IDS-TRACE * ALTER NO.- 282  (5)
          DATREC          RDM X1          (6)          (7)
GET DATMAT          120/ 1  0992          0000          00000006          00005          WKGWK          YYY          0068
          BASE2          YYMON          PERMAX          (12)          FSTMON
          0001          0001          07          SFX          0001
***** IDS-TRACE * ALTER NO.- 303  (5)
          DATREC          MAT CALDAT          (6)          (7)
CHN DATDET          120/ 2  0992          9999          STA ACTDAT          CODDAT          (1)
***** IDS-TRACE * ALTER NO.- 319  (5)
          DATREC          MAT CALDAT          (6)          (7)
MDFY DATDET          120/ 2  0992          9998          STA ACTDAT          CODDAT          (1)
          *          (14)

```


Figure 43. Sample .QSTC Output

QUTF

Verify and Print Utility Subroutine (.QUTF)


QUTF verifies the integrity of a page and formats and prints I-D-S data base information received from QUTU, QUTL or QUTD.

The calling sequences are:



This entry point must be called first to initialize .QUTF. ARG1 is the name of the file control block to which the dump output is sent. Normally, this is the file control block for SYSOUT, P*.

ARG2 is the symbolic location of four words that are included in the title line of the dump output. Normally, it is name and version of QUTU, which produces the output from QUTD, QUTL, or QUTU.



This entry point is called for each page that is to be verified.

ARG1 is the location of a word which contains the 24 bit page reference code, right justified.

ARG2 is the address of the first word of the page to be verified.

ARG3 is the location of a word which specifies whether the page will be dumped on the printer via SYSOUT. If the word is zero, no printing will be performed. If the word is nonzero, the page will be printed. In addition, if this word is nonzero it must be preceded by and followed by two words of zeroes.

ARG4 is the location of the user's alternate exit which is taken whenever a page cannot be verified.


The following checks are performed to verify the integrity of a page:

- The page number supplied by the caller (ARG1) equals the page number in the input record.
- Every line present in the page has its line flag properly set.
- The sum of record sizes equals the active page size.
- Line flags are not set for lines that are not contained in the page.

If any one of these tests fails, an appropriate error message is written on the execution report followed by a snapshot of the page in error. The registers shown in the panel portion of the snapshot dump display the following information:

- X0 The page number supplied by the caller in argument 1.
 - X1 The current word address within the page where processing was being performed when the error occurred.
 - X2 The current character position in the word described by index register 1.
 - X3 The usable page size expressed in characters.
 - X4 The available space expressed in characters.
 - X5 The active page size expressed in characters.
 - X6 The number of characters in the page which have already been processed.
 - X7 The number of the current line being processed.
- AR/
 QR The current status of the available line flags, left justified. These flags are taken from working storage and some bits may not be present for those lines already processed.


As each page is verified, secondary entry points of .QUTF are called to format and print the page, if required. These entry points are described below:



This entry point is called at the beginning of each page. It supplies information to .QUTF concerning the page number and the active page size.

ARG1 is the location of the page number, in binary, right justified.

ARG2 is the location of the active page size, in binary, right justified.



The third entry point is called to print each line. ARG1 is the location of the word number within the page for this line. The value is binary, right justified.

ARG2 is the location of a tally word containing the address and starting character position of the line.

ARG3 is the location of an indicator. If ARG3 is 0, the Page Header (line 0) is sent for printing. If ARG3 is ≠0 and negative, a normal line is sent for printing.

Printer Format

The format of pages selected for printer output is shown below:

PAGE: XXXXX XX ACTIVE PAGE SIZE: XXXX CH.

WD: LN: TYPE:

XXX	XX	XXXX	OCTAL	OCTAL	OCTAL	OCTAL	BCD
			OCTAL	OCTAL	OCTAL	OCTAL	BCD
			OCTAL	OCTAL	OCTAL	OCTAL	BCD
XXX	XX	XXXX	OCTAL	OCTAL	OCTAL	OCTAL	BCD

Execution Report

The output produced by the .QUTF subroutine is written on the file provided by the user in his call to .QUTF1. The report code is 25(10). Output is produced by calling the PRINT and EPRINT subroutines of GEFRC. The GEFRC subroutine IOEDIT is used for page numbering and format control.

Operation

QUTF is used by QUTD and QUTL to print data base pages in the desired format. It is made available to the utility routines from the subroutine library through the use of the SYMREF feature of GMAP. QUTF is not freestanding and cannot be called except through the user's own program.

Sample Output

An I-D-S Selective Tape Dump report using .QUTF is shown on the following page.

100	34	50	4200620021	000000000003	000100017125	
103	35	50	430062002100	000000060700	0100017206	
105	36	50	44	000200210000	000103010001	00017177
108	37	50	4500	020021000000	010402000100	017227
111	38	50	460062	002100000001	040000010001	7145
114	39	50	47006200	210000000101	020001000172	25
117	40	50	5000620021	000000000505	000100017215	
120	41	50	510062002100	000004020500	0100017156	
122	42	50	52	000200210000	000207030001	00017175
125	43	50	5300	020021000000	030206000100	017232
128	44	50	540062	002100000003	050500010001	7162
131	45	50	55006200	210000000403	000001000172	31
134	46	50	5600620021	000000040210	000100017155	
137	47	50	570062002100	000001060000	0100017201	
139	48	50	60	000200210000	000307060001	00017221
142	49	50	6100	020021000000	040701000100	017222
145	50	50	620062	002100000003	060100010001	7133
148	51	50	63006200	210000000206	020001000172	41
151	52	50	6400620021	000000021101	000100017170	
154	53	50	650062002100	000002030609	0100017104	
156	54	50	66	000200210000	000301020001	00017225
159	55	50	6700	020021000000	030403000100	017237
162	56	50	700062	002100000002	110700010001	7106
165	57	50	71006200	210000000111	100001000171	30
168	58	50	7200620021	000000020207	000100017165	
171	59	50	730062002100	000000040409	0100017103	
173	60	50	74	000200210000	000204100001	00017113
176	61	50	7500	020021000000	020711000100	017164
179	62	50	760062	002100000001	061100010001	7132
182	63	50	77006200	210000000103	040001000171	27

K0S0A0000030101Z
 L0S0A0000670101+6
 M0S0A0001310101Z
 N0S0A0001420101+G
 O0S0A0001400101Z
 P0S0A0001120101+E
 Q0S0A0000550101+I
 R0S0A0004250101Z
 -0S0A0002730101Z#
 S0S0A0003260101+8
 *0S0A0003550101ZS
)0S0A0004300101+I
)0S0A0004280101Z)
 '0S0A0001600101+1
 +0S0A0003760101+K
 /0S0A0004710101+8
 S0S0A0003610101Z,
 T0S0A0002620101+J
 U0S0A0002910101ZY
 V0S0A0002360101Z4
 W0S0A0003120101+R
 X0S0A0003430101+\
 Y0S0A0002970101Z6
 Z0S0A0001980101ZH
 +0S0A0002270101ZV
 ,0S0A000440101Z3
 X0S0A0002480101Z#
 =0S0A0002790101ZU
 "0S0A0001690101Zg
 !0S0A0001340101ZG

WD:	LN:	TYPE:	000172775000	017200242777	77777777700	00000000	01+1001+0DG!!!!!100000
0	0	1000	000172775000	017200242777	77777777700	00000000	10S0A0001630101Z"
3	1	50	0100	020021000000	010603000100	017176	20S0A0001840101+K
6	2	50	020062	002100000001	100400010001	7242	30S0A0002150101Z-
9	3	50	03006200	210000000201	050001000171	72	40S0A0001050101ZP
12	4	50	0400620021	000000010005	000100017147		50S0A0002090101+3
15	5	50	050062002100	000002001100	0100017203		60S0A0000700101ZF
17	6	50	06	000200210000	000007000001	00017125	70S0A0000990101Z+
20	7	50	0700	020021000000	001111000100	017140	80S0A0001200101ZM
23	8	50	100062	002100000001	020000010001	7144	90S0A0001510101Z'
26	9	50	11006200	210000000105	010001000171	57	(0S0A0000410101Z,
29	10	50	1200620021	000000000401	000100017173		#0S0A0000170101+L
32	11	50	130062002100	000000010700	0100017243		00S0A0000350101Z\
34	12	50	14	000200210000	000003050001	00017137	!0S0A0000560101Z{
37	13	50	1500	020021000000	000506000100	017112	>0S0A0000870101+7
40	14	50	160062	002100000000	100700010001	7207	?0S0A0004570101Z!
43	15	50	17006200	210000000405	070001000171	31	0S0A0003050101ZD
46	16	50	2000620021	000000030005	000100017124		

Appendix A. Reserved Words

I-D-S RESERVED WORDS

I-D-S uses all the reserved words specified for COBOL. In addition, it employs the reserved words listed below. The user must avoid using words on both these lists for data-names.

ABORT	EACH	PROCESS
ALLOWED	ERROR-REFERENCE	RANDOMIZE
ANY	FIELD	REC-FILE
AUTHORITY	FIRST-REFERENCE	RECORD-TYPE
AUTHORITY-KEY	HEAD	REPLACE
BUFFER	IDS	RETRIEVAL
CALC	IDS-SPECIAL-NAMES	RETRIEVE
CCBLOC	INTERVAL	SORTED
CCBLOXK	LAST-REFERENCE	STORE
CHAIN	LINKED	SYN
CHAIN-ORDER	MASTER	SYNONYM
CURRENT	MATCH-KEY	TABLE
DEBUG	MD	TRACE
DELETE	MODIFY	UNIQUE
DIRECT	NEAR	UPDATE
DIRECT-REFERENCE	PAGE-RANGE	VIA
DUPLICATES	PRIOR	WITHIN
		WORKING

I-D-S GENERATED GMAP SYMBOLS

GMAP symbols defined in the location field must not conflict with reserved system symbols. (See GE-600 Line Programming Reference Manual, CPB-1004.) Symbols in the form LLN>NN, where L is any letter and N is a number, must not be defined in the location field of GMAP statements.

Appendix B. I-D-S Error Conditions

Two types of error conditions may occur during I-D-S program execution. The code, I-D-S source, and description for error conditions of both types are shown in the following sections.

DATA-DEPENDENT ERROR CONDITIONS

Testing for data-dependent error conditions must be incorporated in the procedural logic of the user program. Codes for this type of error are stored in the communication cell ERROR-REFERENCE for reference by the user program. The various codes are listed in the following table. With each code is shown the I-D-S source of the error condition and its description as printed by the TRACE option of the USE statement. This description will be printed if the TRACE option is selected. (See the USE description in Chapter 3 for an example of TRACE output.)

The key to abbreviations in the descriptions is shown below:

RT - record type MT - master record type
REF - reference code DT - detail record type
XXXX - variable inserted by TRACE

<u>Error Code</u>	<u>Source</u>	<u>Description from Trace</u>
R01	QASC	No current record reference code record type XXXX
R02	QASC	Record retrieved logically deleted RTXXXX REFXXXXXXXX
R03	QASC	Request retrieval of record RTXXXX got RTXXXX
R04	QASC	No record on chain MTXXXX-DTXXXX or structure error for record type XXXX
R05	QGTC	Retrieve current, current equals zero rec-type XXXX

R06	QGTD	Retrieve direct and direct reference equals zero
R07	QGTD	Retrieve direct and record is logically deleted
R08	QMRA	Line number not on specified page ref code XXXXXXXXX
R09	QBIC QSMT	Page requested is not allocated reference code XXXXXXXXX
R10	QDLT	Illegal delete request of RTXXXX want RTXXXX
R11	QMDF	Illegal modify request of RTXXXX want RTXXXX
R12	QMNO QCAL	Working storage for page range zero record type XXXX
D01	QTLN	Store of unallowed duplicate record type XXXX
S01	QMNO	No space available for record type XXXX

ERROR CONDITIONS CAUSING ABORT

Improper use of I-D-S functions, invalid data file definition, and unrecoverable hardware malfunctions cause an automatic trace and abort of the user program. In addition, a memory dump occurs.

Whenever an I-D-S program aborts, the I-D-S data file is first CLOSED, with the appropriate pages restored to the mass storage device.

If the trace cannot acquire a link on mass storage for an overlay, the following error comment may occur:

CANNOT TRACE ERROR, INADEQUATE SPACE

The various abort reason codes are listed in the following table. With each code is shown the I-D-S source of the error condition and its trace description.

Note that while they are included in this table, codes 65 through 88 are not associated with an abort condition, but have been added solely to permit the printing of an appropriate error message while TRACE-ing the non-fatal errors discussed above. These codes may be encountered in a memory dump, or among the inner workings of the I-D-S subroutines, but will otherwise be invisible to the user.

Rev. August 1971

The key to abbreviations in the descriptions is shown below:

RT - record type	MT - master record type
REF - reference code	DT - detail record type
CC - communication control	XXXX - variable inserted by TRACE

<u>Reason Code</u>	<u>Source</u>	<u>Description from Trace</u>	*
04	QAUT	Authority key does not match record type XXXX	█
05	QSMT	No records returned from sort	█
06	QRLN	Read error - check error reference in CC block	
07	QRLN	Record retrieved logically deleted RTXXXX REFXXXXXXXX	
08	QRLN	No position prior pointer chain MTXXXX - DTXXXX	
09	QRLN	No detail definitions for this chain MTXXXX	
10	QASC	Retrieval via missing for record type XXXX	
11	QASC QDLT QSTO	Detail in too many chains record type XXXX or/master of too many chains record type XXXX	█
12	QASC	No unique field for primary record - record type XXXX	
13	QGTD QRLN	No record definition has been established	█
14	QHED	Chain next equal zero chain - MTXXXX-DTXXXX	█

15	QDLT QMDF QSTO	Processing mode not up-date
16	QMDF QMOV	Field of modify/move not in record type XXXX
17	QDLT	No current record of program on delete
18	QFWD	Retrieve next in chain no current exists MTXXXX-DTXXXX
19	QGDE	Invalid control definition record type XXXX
20	QGDE	Control field error, equals zero for record type XXXX
24	QSTO	No unique field on store for record type XXXX
25	QSTOR	No storage chain specified for record type XXXX
26	QTYP QRLN	Record retrieved not specified for chain MTXXXX-DTXXXX
27	QDLT	Delete action list is invalid
29	QUDC QRLN	No position next pointer chain MTXXXX-DTXXXX
30	QMRA	Record size conflict for record type XXXX
31	QSBF QSMT	Attempt to write not update, reference code XXXXXXXXX
32	QBIC QSMT	Invalid page size for reference code XXXXXXXXX
33	QIV3 QIV4 QFWD	Page requested is not allocated reference code XXXXXXXX
34	QIOS	Read/write error
35	QSMT QBIC	No empty buffer for REND

Rev. August 1971

36	QRDN	Attempted update while in READ only mode
52	QTLN	Record cannot be linked chain MTXXXX-DTXXXX
53	QTLN	Error trying to retrieve prior chain MTXXXX-DTXXXX
54	QTLN	Error trying to retrieve next chain MTXXXX-DTXXXX
55	QTLN	Error trying to retrieve new chain MTXXXX-DTXXXX
56	QBIC	Page read is not page requested, reference code XXXXXXXX
57	QDLN	Next of chain is equal to zero chain MTXXXX-DTXXXX
58	QTLN	Attempt to link, next equals zero chain MTXXXX-DTXXXX
59	QIV3	Inventory read not one requested
60	QTLN QRLN	Next in chain not retrievable chain MTXXXX-DTXXXX
61	QOPE	Error in file definition at open time
65		(See Error Code "R01")
66		(See Error Code "R02")
67		(See Error Code "R03")
68		(See Error Code "R04")
69		(See Error Code "R05")
70		(See Error Code "R06")
71		(See Error Code "R07")
72		(See Error Code "R08")
73		(See Error Code "R09")
74		(See Error Code "R10")

75		(See Error Code "R11")
76		(See Error Code "R12")
80		(See Error Code "D01")
88		(See Error Code "S01")
129	QCHN QDBG QDLT QGET QGTC QGTD QGTE QHED QMDF QMOV QRLN QSTO	File unopened but access requested
130	QCHN QDBG QDLT QGET QGTC QGTD QGTE QHED QMDF QMOV QRLN QSTO	Primary subroutine entry during error processing
All others		Error code undefined

Rev. August 1971

Appendix C. GE-600 COBOL/I-D-S/FORTRAN Communication and Overlaying

This appendix explains the procedures and techniques to follow when overlaying a COBOL program, using the Integrated Data Store (I-D-S) software and mixing FORTRAN programs with COBOL or the COBOL/I-D-S software on a GE-600 system.

OVERLAYING A COBOL PROGRAM

Basis for Overlaying

Most programs should be segmented and overlayed when they become large. The memory allocated to a program will vary among sites. That is, some sites will have a billing formula to compute the cost of a computer run. If a particular computer run requires, for example, more than 40k of memory, the user's cost will have a very drastic increase after this limit has been reached.

In a multiprogramming system, the more memory required for a particular program decreases the effectiveness of the overall system. So, there is a justification for increasing the charge for a program when a set memory limit has been exceeded.

Many programs can be overlayed to reduce their memory requirements. These programs may have sections that are utilized only once or just a few times. These sections definitely do not have to reside in memory for the entire duration of a computer run. Other sections which do not have direct references to one another can be swapped in and out of memory, also under user control.

Segmentation

To accomplish overlaying, the program must be divided into subroutines, subprograms, or segments, whichever term you wish to choose. The term subprogram is used in this appendix. This program, when divided, will consist of numerous subprograms, each compiled separately or each appearing to be an entity or program.

Thus, each subprogram will be a separate COBOL compilation, each with an Identification Division, Environment Division, Data Division, and Procedure Division. Each program will have a uniqueness to depict that they are subprograms. These features, imbedded in the programs, are various transfers, entry points, exits, and common data storage areas.

Communication Between Subprograms

Once a subprogram exists, the means of communicating with the other subprograms (and also examining constant or variable data used in different subprograms) must be accomplished.

First, the method of passing constant or variable information between the subprograms. In COBOL, use the labeled common area method. These areas are defined in each subprogram that use any of the constant or variable information. The following example will show how to set up the labeled common areas so that the different subprograms can examine the same data.

Subprogram MAIN

```
000010 IDENTIFICATION DIVISION.
000020 PROGRAM-ID. MAIN.
      .
      .
000140 ENVIRONMENT DIVISION.
      .
      .
000180 SPECIAL-NAMES.
000190     BLOCK 31 IS ENTRY-REC THRU LAST-REC.
      .
      .
000320 DATA DIVISION.
000330 FILE SECTION.
      .
      .
000500 WORKING-STORAGE SECTION.
000510 01  ENTRY-REC.
000520     02  OTHER-LEVELS SIZE IS 48 NUMERIC.
000530 01  LAST-REC.
000540     02  MORE-LEVELS SIZE IS 42 NUMERIC.
```

Subprogram NEXTPG

```
000010 IDENTIFICATION DIVISION.
000020 PROGRAM-ID. NEXTPG.
      .
      .
000120 ENVIRONMENT DIVISION.
      .
      .
000150 SPECIAL-NAMES.
000160     BLOCK 31 IS REC-ENTRY THRU REC-LAST.
      .
      .
000400 DATA DIVISION.
000410 FILE SECTION.
      .
      .
000550 WORKING-STORAGE SECTION.
000560 01  REC-ENTRY.
000570     02  DATA-HERE SIZE IS 48 NUMERIC.
000580 01  REC-LAST.
000590     02  MORE-DATA SIZE IS 42 NUMERIC.
      .
      .
```

The preceding example shows the entries necessary for communication in the Environment Division and Data Division of two subprograms. The labeled common area is the same in both since Block 31 was mentioned, and the size of the 01 records is consistent.

At load time, one labeled common area called C31 (COBOL always prefixes the integer with the Character C) will be generated. The total size will be 90 characters. In subprogram MAIN, references to the common area (C31) will be by the name OTHER-LEVELS and MORE-LEVELS; whereas in subprogram NEXTPG, references to this same common area (C31) will be by the name DATA-HERE and MORE-DATA.

Since subprograms MAIN and NEXTPG are compiled separately, the names can be the same or different. The important concepts to remember from this example are that only one labeled common area (C31) will be generated when subprogram MAIN is loaded, and any subsequent subprogram referring to the identical area (C31) will have its references adjusted to this area.

When a COBOL program is divided into subprograms, transferring control during execution from one subprogram to another is done by using the CALL statement. If a return to the calling subprogram is desired, then the EXIT statement is used.

The following example shows the basic method of using the CALL and EXIT statements.

Subprogram SNOOPY

```
00001 010010 IDENTIFICATION DIVISION.  
00002 010020 PROGRAM-ID. SNOOPY.  
.  
00149 040010 PROCEDURE DIVISION.  
.  
00191 041080     ENTER LINKAGE MODE.  
00193 041100     CALL CHKSEG  
.  
.
```

Transfer is to the PROGRAM-ID whose location is the first executable statement in the PROCEDURE DIVISION of subprogram CHKSEG.

Subprogram CHKSEG

```
00001 010010 IDENTIFICATION DIVISION.  
00002 010020 PROGRAM-ID. CHKSEG.  
.  
00092 040010 PROCEDURE DIVISION.  
.  
00104 043120 200-CALL-CK-END.  
00105 043150     EXIT.  
.  
.
```

When EXIT is reached, execution returns to the next statement after CALL CHKSEG in subprogram SNOOPY.

NOTE: This example consists of excerpts taken from the program included with this appendix.

Transferring control to entries other than the PROGRAM-ID is accomplished by defining ENTRY POINTS in the program referred to. By using the ENTRY POINT statement, a SYMDEF is generated making entry possible at that particular point from any other subprogram.

When ENTRY POINT is written in a subprogram to return to the calling subprogram, the EXIT statement with the name of this ENTRY POINT is written.

The following illustrates the proper usage of the ENTRY POINT and EXIT.

```
$   FORTRAN
    COMMON/C20/ITABLE(20)
      .
      .
    CALL SNOOPY
      .
      .
    CALL ENTABC
      .
      .
```

The CALLs above are from a FORTRAN subprogram. They could have been from a COBOL subprogram which had ENTER LINKAGE MODE preceding each CALL.

```
-----
$   COBOL
00001 010010 IDENTIFICATION DIVISION.
00002 010020 PROGRAM-ID. SNOOPY.
      .
      .
00150 040022 PROCEDURE DIVISION.
      .
      .
00240 044014   ENTER LINKAGE MODE.
00241 044015   ENTRY POINT ENTABC.
00242 044016   ENTER COBOL.
      .
      .
00349 045261 309-PROGRAM-EXIT.
00350 045262   EXIT ENTABC.
00351 045263 310-SNOOPY-EXIT.
00352 045280   EXIT PROGRAM.
```

NOTE: This example consists of excerpts taken from the program included with this appendix.

Overlaying Procedure

The program is now chopped into many subprograms; each contains the necessary statements to refer to other subprograms.

To overlay, a few more statements have to be inserted into the subprograms. These statements are the CALL's to load specific subprograms from the H* file. In an overlay job, the overlays are not retained in memory but are stored on a peripheral to be loaded only when requested by the user. (See GE-600 Line General Loader, CPB-1008 for a complete explanation of the general overlaying method.)

There are two subroutines in the subroutine library (L*) to load the overlays. They are LINK and LLINK. When overlaying a program, the CALL LLINK loads the overlay and returns control to the statement following the CALL. The CALL LINK loads the overlay and returns control to the overlay. It is not possible to return to the statement following the CALL LINK after executing the overlay. Use the CALL LLINK so that you can retain control in a situation where a main subprogram will control transfer to an overlay brought into memory.

The following example illustrates the procedure to follow when overlaying a COBOL program. In the example, the subprogram SNOOPY resides in memory the duration of the execution, and subprograms CHKSEG, SAVSEG, and LOASEG are loaded into memory by the CALL LLINK statements located in SNOOPY.

```

$   SNUMB      12345
$   IDENT      HA963,ERICKSON
$   COBOL
00001 010010 IDENTIFICATION DIVISION.
00002 010020 PROGRAM-ID. SNOOPY.
      .
      .
00033 020010 DATA DIVISION.
      .
      .
00052 020300 WORKING-STORAGE SECTION.
00054 020310 77   SEG-1  PICTURE X(6) VALUE IS "LINKAA".
00055 020320 77   SEG-2  PICTURE X(6) VALUE IS "LINKBB".
00056 020330 77   SEG-3  PICTURE X(6) VALUE IS "LINKCC".
      .
      .
00149 040010 PROCEDURE DIVISION.
      .
      .
00191 041080     ENTER LINKAGE MODE.
00192 041090     CALL LLINK USING SEG-1
00193 041100     CALL CHKSEG
      .
      .
00199 041160     ENTER LINKAGE MODE.
00200 041170     CALL LLINK USING SEG-3
00201 041180     CALL LOASEG
      .
      .
00207 042030     ENTER LINKAGE MODE.
00208 042040     CALL LLINK USING SEG-2
00209 042050     CALL SAVSEG
      .
      .

```

```

-----

$   LINK      LINKAA
$   COBOL
00001 010010 IDENTIFICATION DIVISION.
00002 010020 PROGRAM-ID. CHKSEG.
      .
      .
00092 040010 PROCEDURE DIVISION.
      .
      .
00104 043120 200-CALL-CK-END.
00105 043150     EXIT.
-----

```

```

$ LINK LINKBB, LINKAA
$ COBOL
00001 010010 IDENTIFICATION DIVISION.
00002 010020 PROGRAM-ID. SAVSEG.
.
.
00091 040010 PROCEDURE DIVISION.
.
.
00103 043200 200-CALL-SA-END.
00104 043230 EXIT.
-----

```

```

$ LINK LINKCC, LINKBB
$ COBOL
00001 010010 IDENTIFICATION DIVISION.
00002 010020 PROGRAM-ID. LOASEG.
.
.
00091 040010 PROCEDURE DIVISION.
.
.
00103 043160 200-CALL-LO-END.
00104 043190 EXIT.
-----

```

NOTE: This example consists of excerpts taken from the program included with this appendix.

USING I-D-S WITH A COBOL OVERLAYED PROGRAM

Since the I-D-S statements are coded within the COBOL subprograms, there are certain procedures that must be considered.

A Communications Control Block (CCBLOC) must be established in a labeled common area. Normally, the CCBLOC is located in the COBOL program and the remaining structure is located in a labeled common area (.IDS...). When a program is divided into subprograms, each subprogram must be able to examine the CCBLOC. If it is isolated in the first subprogram loaded, then the remaining subprograms loaded will not be able to communicate with the CCBLOC.

To establish the CCBLOC in a labeled common area, write the following coding:

```
00014 010060 ENVIRONMENT DIVISION.  
00018 010091 SPECIAL-NAME.  
00023 010096     BLOCK nn is CCBLOXX.  
                (nn is a 1 or 2 digit integer).
```

This is essentially the most important feature to realize when overlaying a COBOL/I-D-S program.

Another method to consider is placing the structure in a different labeled common area other than the .IDS.. area. Since the program is segmented, it is now possible to execute more than one I-D-S file. In this situation the first file must be closed before the second can be opened and executed. In other words, only one file can be in the open mode. The reason for this is that the page buffers for a file must be flushed before executing another file.

FORTRAN - INTERFACING WITH COBOL AND I-D-S

A FORTRAN program can easily communicate with the COBOL/I-D-S software. The knowledge that a FORTRAN user needs of COBOL is minimal, and if a FORTRAN user would like to utilize the I-D-S features, again the COBOL coding required and understanding can be minimal.

How to Communicate Between Compilers

Reiterating what was mentioned regarding COBOL segmentation--

1. Labeled common areas generated by the COBOL compiler are a one or two integer number always prefixed by the Letter C.
2. Entries into the Procedure Division can be made by referring to the PROGRAM-ID or ENTRY POINT name.
3. Return to the calling program is via the terminal EXIT statement of the EXIT name statement.

With these facts about the COBOL compiler, a FORTRAN user can create a program using these two together.

The FORTRAN subprogram contains labeled common areas corresponding to the COBOL areas. Variables and/or constants stored in these areas should have the same classification. That is, if a variable has been defined as floating point in one subprogram, it is defined as floating point in the other. Illustration of the above statements is depicted in the following examples with the addition of I-D-S.

```

$   SNUMB      24788
$   IDENT      HA963,ERICKSON
$   OPTION     FORTRAN
$   FORTRAN
SUBROUTINE GENO
COMMON/C35/IDATA,FLTNUM,IADD, -----
      .
      .
CALL MAINPG
      .
      .
CALL SECPRG
      .
      .
END
$   ENTRY      GENO
$   USE        .QMAX/1/, .QAREA/2000/, .QMIN/1/
$   IDS
000010 IDENTIFICATION DIVISION.
000020 PROGRAM-ID. MAINPG.
      .
      .
020010 ENVIRONMENT DIVISION.
020020 SPECIAL-NAMES.
020030     BLOCK 20 IS CCBLOXK.
020040     BLOCK 35 IS ENTRY-REC THRU LAST-REC.
      .
      .
030100 IDS SECTION
030101 MD  IDS-PORTION PAGE CONTAINS 1920 CHARACTERS
030102     FILE CONTAINS 1000 PAGES.
030103 01  ENTRY-REC -----
030104     02  DATA-HERE SIZE IS 9(6) COMPUTATIONAL-3.
030105     02  MORE-DATA SIZE IS 9(8) COMPUTATIONAL-2.
030106     02  ADD-MORE-DATA SIZE IS 9(6) COMPUTATIONAL-3.
      .
      .
030115 01  INNER-RECORDS -----
      .
      .
030130 01  LAST-REC -----
      02  THATS-ALL SIZE IS 9(7) COMPUTATIONAL-2.
      .
      .

```

```

      .
      .
040010 PROCEDURE DIVISION.
      .
040200      GO TO MAIN-EXIT.
040201      ENTER LINKAGE MODE.
040202      ENTRY POINT SECPRG.
040203      ENTER IDS.
040204      RETRIEVE ENTRY-REC.
040205 BACK-TO-FORT.
040206      EXIT SECPRG.
040207 MAIN-EXIT.
040208      EXIT.
040209      END PROGRAM.
$      EXECUTE
$      DISC      DF,X2R,2R
$      DATA      .Q
IDS      CREATE FILECODE/DF/,BASESIZE/1000/,RANGE/1,1000/,
          ETC      PAGESIZE/320/
$      ENDJOB

```

The contents of the labeled common area, C35, actually contain the I-D-S working storage area for all 02 levels beginning at record ENTRY-REC through record LAST-REC. Thus the equivalent values in C35 are the following:

<u>FORTRAN</u>	<u>COBOL</u>	<u>TYPE</u>
IDATA	DATA-HERE	Fixed Point Integer
FLTNUM	MORE-DATE	Floating Point
IADD	ADD-MORE-DATE	Fixed Point Integer

Consideration When Mixing Software

The 01 levels are always begun at an even memory location. Problems could occur when trying to pass information between COBOL and FORTRAN in the labeled common areas. To avoid this, check the labeled common size generated from the COBOL compiler and adjust the FORTRAN subprogram so that the correct data will be examined.

FORTRAN programs, at execution time, have file control blocks and buffers generated by the loader in the unused portion of slave memory. I-D-S checks word 37 (octal) of the slave prefix area to determine the size of unused memory and establishes as many page buffers as possible in this area. So now there is a major conflict of interest. Solution: At load time, create a labeled common area for the page buffers and other I-D-S control tables by inserting a \$ USE control card. Now the FORTRAN I/O routines can use unused slave memory without conflict.

05091 01 02-05-70 14.810

```
1      COMMON/C20/ITABLE(24)/C21/ICK,ILO,ISA
2      *
3      CALL SNOOPY
4      *
5      CALL ENTABC
6      *
7      ITOT=ICK+ILO+ISA
8      PRINT 11, ICK
9      11 FORMAT(42H NUMBER OF CHECKING ACCOUNT RECORDS READ =,16)
10     PRINT 12, ILO
11     12 FORMAT(30H NUMBER OF LOAN RECORDS READ =,16)
12     PRINT 13, ISA
13     13 FORMAT(40H NUMBER OF SAVING ACCOUNT RECORDS READ =,16)
14     PRINT 15, ITOT
15     15 FORMAT(31H TOTAL NUMBER OF RECORDS READ =,16)
16     STOP
17     END
```

23260 WORDS OF MEMORY USED BY THIS COMPILATION

NOTE: This is a FORTRAN program that was compiled illustrating just a labeled common area (C20) and two CALL statements which reference COBOL programs.

85091 01 02-05-70 14.811

PREFACE

PROGRAM BREAK 132
COMMON LENGTH 0
V COUNT BITS 5

PRIMARY SYMDEF ENTRY

..... 0

SECONDARY SYMDEF ENTRY

	BLOCK	LENGTH
1	C20	30
2	C21	3

SYMREF

3 ENTABC
4 .FCNV.
5 .FEXIT
6 .FFIL.
7 .FPRN.
10 SNOOPY

END OF BINARY CARD 00000006

132 IS THE NEXT AVAILABLE LOCATION. GMAP AID 051169
THERE WERE NO WARNING FLAGS IN THE ABOVE ASSEMBLY
** 18715 WORDS OF MEMORY WERE USED BY GMAP FOR THIS ASSEMBLY.

IDS ALTER NOS.

```

00001 010010 IDENTIFICATION DIVISION.
00002 010020 PROGRAM-ID. SNOOPY.
00003 010030 AUTHOR, GEORGE A RUDOLPH.
00004 010040 DATE-WRITTEN, MAY 1969.
00005 010050 INSTALLATION, G E - PHOENIX.
00006 010051 REMARKS, THIS PROGRAM LOADS DATA FROM THE CARD READER
00007 010052 ONTO A TEMPORARY DISC FILE
00008 010053 DEPENDING ON THE ACCOUNT TYPE ROUTINES ARE
00009 010054 CALLED TO STORE THE DATA
00010 010055 WHEN ALL OF THE RECORDS HAVE BEEN
00011 010056 STORED ON THE DATA BASE THEY ARE
00012 010057 RETRIEVED AND PRINTED ON A CONTROL
00013 010058 REPORT.
00014 010060 ENVIRONMENT DIVISION.
00015 010070 CONFIGURATION SECTION.
00016 010080 SOURCE-COMPUTER, GE-635.
00017 010090 OBJECT-COMPUTER, GE-635.
00018 010091 SPECIAL-NAMES.
00019 010092 GETIME IS TODAY'S-DATE.
00020 010093* DEFINES A LABELED COMMON AREA FOR THE IDS COMMUNICATION
00021 010094* CONTROL BLOCK AND RECORD DEFINITIONS FOR SEGMENTATION
00022 BLOCK 21 IS NUCK THRU NUSA.
00023 010095 BLOCK 10 IS CCBLOXK.
00024 010096 BLOCK 20 IS ENTRY-REC THRU LOAN-REC.
00025 010200 INPUT-OUTPUT SECTION.
00026 010210 FILE-CONTROL.
00027 010215 SELECT PRINT-UNIT ASSIGN TO PR FOR LISTING.
00028 010220 SELECT CARD-READER ASSIGN TO CR FOR CARDS.
00029 010225* ASSIGN IDS FILE NAME AND DEVICE
00030 010230 SELECT IDS TEST-FILE ASSIGN TO TF.
00031 010240 I-O-CONTROL.
00032 010245 APPLY SYSTEM STANDARD FORMAT ON PRINT-UNIT.
00033 010250 APPLY SYSTEM STANDARD FORMAT ON CARD-READER.
00034 020010 DATA DIVISION.
00035 020020 FILE SECTION.
00036 020021 FD PRINT-UNIT
00037 020022 LABEL RECORDS ARE STANDARD
00038 020023 DATA RECORD IS PRINT-LINE.
00039 020024 01 PRINT-LINE PICTURE X(132).
00040 020030 FD CARD-READER
00041 020040 LABEL RECORDS ARE STANDARD
00042 020050 DATA RECORD IS CARD-IN.
00043 020060 01 CARD-IN.
00044 020070 02 ACCT-TYPE PICTURE XX.
00045 020080 88 LOAN-ACCT VALUE "LO".
00046 020090 88 SAVE-ACCT VALUE "SA".
00047 020200 88 CHECK-ACCT VALUE "CK".
00048 020210 02 CUST-NO-IN PICTURE 9(6).
00049 020220 02 ACCT-NO-IN PICTURE 9(6).
00050 020230 02 CUST-NAME-IN PICTURE X(26).
    
```

IDS ALTER NOS.

```

00051 020240 02 AMOUNT-IN PICTURE 9(10)V99.
00052 020250 02 FILLER PICTURE X(31).
00053 020300 WORKING-STORAGE SECTION.
00054 020305* CODING TO DEFINE THE LINKAGE FOR SEGMENTATION
00055 020310 77 SEG-1 PICTURE X(6) VALUE IS "LINKAA".
00056 020320 77 SEG-2 PICTURE X(6) VALUE IS "LINKBB".
00057 020330 77 SEG-3 PICTURE X(6) VALUE IS "LINKCC".
00058 77 NUCK PICTURE 9(6) COMP-1.
00059 77 NULO PICTURE 9(6) COMP-1.
00060 77 NUSA PICTURE 9(6) COMP-1.
00061 020340 01 WORK-LINE.
00062 020350 02 HEAD-ONE.
00063 020360 03 FILLER PICTURE X(41).
00064 020370 03 TITLE-1 PICTURE X(49).
00065 020380 03 FILLER PICTURE X(42).
00066 020390 02 HEAD-TWO REDEFINES HEAD-ONE.
00067 020400 03 FILLER PICTURE X(62).
00068 020410 03 MONTH-P PICTURE Z9.
00069 020420 03 DASH-1 PICTURE X.
00070 020430 03 DAY-P PICTURE Z9.
00071 020440 03 DASH-2 PICTURE X.
00072 020450 03 YEAR-P PICTURE 99.
00073 020460 03 FILLER PICTURE X(62).
00074 020470 02 HEAD-THREE REDEFINES HEAD-TWO.
00075 020480 03 FILLER PICTURE X(24).
00076 020490 03 TITLE-10 PICTURE X(19).
00077 020500 03 FILLER PICTURE X(8).
00078 020510 03 TITLE-20 PICTURE X(19).
00079 020520 03 FILLER PICTURE X(8).
00080 020530 03 TITLE-30 PICTURE X(10).
00081 020540 03 FILLER PICTURE X(14).
00082 020550 03 TITLE-40 PICTURE X(6).
00083 020560 03 FILLER PICTURE X(32).
00084 020570 02 DETAIL-LINE REDEFINES HEAD-THREE.
00085 020580 03 FILLER PICTURE X(28).
00086 020590 03 CUST-NO-P PICTURE 9(6).
00087 020600 03 FILLER PICTURE X(16).
00088 020610 03 TYPE-P PICTURE X(8).
00089 020620 03 FILLER PICTURE X(14).
00090 020630 03 ACCT-NO-P PICTURE 9(6).
00091 020640 03 FILLER PICTURE X(9).
00092 020650 03 AMOUNT-P PICTURE Z,ZZZ,ZZZ,ZZZ,99-.
00093 020660 03 FILLER PICTURE X(28).
00094 020670 01 DATE-AND-TIME.
00095 020680 02 MONTH PICTURE 99.
00096 020690 02 DAY PICTURE 99.
00097 020700 02 YEAR PICTURE 99.
00098 020710 02 TIME PICTURE 9(8).
00099 020720 USAGE IS COMPUTATIONAL-1.
00100 020730 01 DISPLAY-FIELD PICTURE 9(8).

```

86222 01 02-05-70 14.799 GE600 INTEGRATED STORE TRANSLATOR ISDL-2 CHG00

IDS ALTER NOS.

00101 030010 IDS SECTION.
01 CCBLOXK ,
02 DIRECT-REFERENCE SIZE IS 8 USAGE IS COMPUTATIONAL-1
SYNCHRONIZED RIGHT.
02 FIRST-REFERENCE SIZE IS 8 USAGE IS COMPUTATIONAL-1
SYNCHRONIZED RIGHT.
02 LAST-REFERENCE SIZE IS 8 USAGE IS COMPUTATIONAL-1
SYNCHRONIZED RIGHT.
02 RECORD-TYPE SIZE IS 4 USAGE IS COMPUTATIONAL-1
SYNCHRONIZED RIGHT.
02 REC-FILE SIZE IS 6 CLASS IS ALPHANUMERIC
VALUE IS "0000TF".
02 ERROR-REFERENCE SIZE IS 3 CLASS IS ALPHANUMERIC
SYNCHRONIZED RIGHT.

00102 030020 MD TEST-FILE
00103 030030 PAGE CONTAINS 1920 CHARACTERS
00104 030040 FILE CONTAINS 100 PAGES;
00105 030050 01 ENTRY-REC
00106 030060 TYPE IS 010
00107 030070 RETRIEVAL VIA CALC CHAIN
00108 030080 PAGE-RANGE IS 1 TO 1.
00109 030090 02 ENTRY-FIELD PICTURE 9(6).
00110 030200 98 CALC CHAIN DETAIL
00111 030210 RANDOMIZE ON ENTRY-FIELD.
00112 030230 98 CUST-NO-CHN CHAIN MASTER
00113 030240 CHAIN-ORDER IS SORTED.
00114 030250 01 CUST-NO-REC
00115 030260 TYPE IS 020
00116 030270 RETRIEVAL VIA CUST-NO-CHN CHAIN.
00117 030290 02 CUST-NO-DSU PICTURE 9(6).
00118 030300 02 CUST-NAME-DSU PICTURE X(26).
00119 031010 98 CUST-NO-CHN CHAIN DETAIL
00120 031020 DUPLICATES NOT ALLOWED
00121 031030 ASCENDING KEY IS CUST-NO-DSU
00122 031040 SELECT CURRENT MASTER.
00123 031050 98 CHECK-CHN CHAIN MASTER
00124 031060 CHAIN-ORDER IS FIRST.
00125 031070 98 SAVE-CHN CHAIN MASTER
00126 031080 CHAIN-ORDER IS FIRST.
00127 031090 98 LOAN-CHN CHAIN MASTER
00128 031200 CHAIN-ORDER IS FIRST.
00129 031210 01 CHECK-REC
00130 031220 TYPE IS 021
00131 031230 RETRIEVAL VIA CHECK-CHN CHAIN.
00132 031250 02 CUST-NO-CK PICTURE 9(6).
00133 031260 02 ACCT-NO-CK PICTURE 9(6).
00134 031270 02 AMOUNT-CK PICTURE S9(10)V99.
00135 031280 98 CHECK-CHN CHAIN DETAIL
00136 031290 SELECT CURRENT MASTER.
00137 032010 01 SAVE-REC

86222 01 02-05-70 14,799 GE600 INTEGRATED STORE TRANSLATOR ISDL-2 CHG00

IDS ALTER NOS,

```

00138 032020 TYPE IS 022
00139 032030 RETRIEVAL VIA SAVE-CHN CHAIN.
00140 032050 02 CUST-NO-SA PICTURE 9(6).
00141 032060 02 ACCT-NO-SA PICTURE 9(6).
00142 032070 02 AMOUNT-SA PICTURE S9(10)V99.
00143 032080 98 SAVE-CHN CHAIN DETAIL
00144 032210 SELECT CURRENT MASTER.
00145 032220 01 LOAN-REC
00146 032230 TYPE IS 023
00147 032240 RETRIEVAL VIA LOAN-CHN CHAIN.
00148 032260 02 CUST-NO-LO PICTURE 9(6).
00149 032270 02 ACCT-NO-LO PICTURE 9(6).
00150 032280 02 AMOUNT-LO PICTURE S9(10)V99.
00151 032290 98 LOAN-CHN CHAIN DETAIL
00152 032320 SELECT CURRENT MASTER.
00153 040010 PROCEDURE DIVISION.
00154 040022 010-START.
00155 040023 ACCEPT DATE-AND-TIME FROM TODAYS-DATE.
00156 040024 OPEN INPUT CARD-READER
00157 040025 OUTPUT PRINT-UNIT.
00158 040030* OPEN IDS DATA BASE
00159 040040 ENTER IDS.
00160 040050 OPEN.
00161 040055 MOVE 000001 TO ENTRY-FIELD.
00162 040057* CREATE ENTRY RECORD
00163 040060 ENTER IDS.
00164 040070 STORE ENTRY-REC
00165 040080 IF ERROR GO TO 100-RET-MST-ENTRY-ERR.
00166 040081 ENTER IDS.
00167 040082 DEBUG CURRENT BUFFER
00168 040083 RECORD
00169 040084 CCBLOC.
00170 040090 020-READ-CARDS.
00171 040100 READ CARD-READER AT END GO TO 310-SNOOPY-EXIT.
00172 040110 IF LOAN-ACCT OR SAVE-ACCT OR CHECK-ACCT
00173 040120 GO TO 030-PROCESS-CARD.
00174 040130 DISPLAY "INVALID CARD CODE".
00175 040140 DISPLAY CARD-IN.
00176 040150 GO TO 020-READ-CARDS.
00177 040160 030-PROCESS-CARD.
00178 040170 ENTER IDS.
00179 040180 RETRIEVE ENTRY-REC RECORD
00180 040190 IF ERROR GO TO 100-RET-MST-ENTRY-ERR.
00181 040200 040-RET-CUST-REC.
00182 040210 ENTER IDS.
00183 040220 RETRIEVE NEXT RECORD OF CUST-NO-CHN CHAIN
00184 040230 IF ERROR GO TO 110-RET-MST-ERR ELSE
00185 040240 IF ENTRY-REC RECORD GO TO 000-STORE-MST-REC
00186 040250 ELSE MOVE.
00187 041010 IF CUST-NO-IN IS EQUAL TO CUST-NO-DSU

```

86222 01 02-05-70 14,799 GE600 INTEGRATED STORE TRANSLATOR ISDL-2 CHG00

IDS ALTER NOS.

```
00188 041020      GO TO 050-STORE-DETAIL.
00189 041030      GO TO 040-RET-CUST-REC.
00190 041040 050-STORE-DETAIL.
00191 041050      IF LOAN=ACCT GO TO 060-STORE-LOAN.
00192 041060      IF SAVE=ACCT GO TO 070-STORE-SAVE.
00193              ADD 1 TO NUCK.
00194 041065*     CALL CHECKING SEGMENT
00195 041070*     CREATES AND STORES CHECK-REC RECORD
00196 041080      ENTER LINKAGE MODE.
00197 041090      CALL LLINK USING SEG-1
00198 041100      CALL CHKSEG
00199 041110      ENTER COBOL.
00200 041130      GO TO 020-READ-CARDS.
00201 041140 060-STORE-LOAN.
00202              ADD 1 TO NULO.
00203 040045*     CALL LOAN SEGMENT
00204 040050*     CREATES AND STORES LOAN-REC RECORD
00205 041160      ENTER LINKAGE MODE.
00206 041170      CALL LLINK USING SEG-3
00207 041180      CALL LOASEG
00208 041190      ENTER COBOL.
00209 041210      GO TO 020-READ-CARDS.
00210 042010 070-STORE-SAVE.
00211              ADD 1 TO NUSA.
00212 042015*     CALL SAVING SEGMENT
00213 042020*     CREATES AND STORES SAV-REC RECORD
00214 042030      ENTER LINKAGE MODE.
00215 042040      CALL LLINK USING SEG-2
00216 042050      CALL SAVSEG
00217 042060      ENTER COBOL.
00218 042080      GO TO 020-READ-CARDS.
00219 042090 080-STORE-MST-REC.
00220 042091*     CREATE AND STORE CUSTOMER NUMBER RECORD
00221 042100      MOVE CUST-NO-IN TO CUST-NO-DSU.
00222 042110      MOVE CUST-NAME-IN TO CUST-NAME-DSU.
00223 042120      ENTER IDS.
00224 042130      STORE CUST-NO-REC
00225 042140      IF ERROR GO TO 150-STORE-CUST-REC-ERR.
00226 042141      ENTER IDS.
00227 042142      DEBUG CURRENT BUFFER
00228 042143      RECORD
00229 042143      CCBLOC.
00230 042150      GO TO 050-STORE-DETAIL.
00231 043010 100-RET-MST-ENTRY-ERR.
00232 043020      DISPLAY "RETRIEVE ERROR".
00233 043030      DISPLAY "FILE ENTRY RECORD".
00234 043040      GO TO 300-WRAP-UP.
00235 043050 110-RET-MST-ERR.
00236 043060      DISPLAY "RETRIEVE ERROR".
00237 043070      DISPLAY "CUSTOMER RECORD".
```

86222 01 02-05-70 14.799 GE600 INTEGRATED STORE TRANSLATOR ISDL-2 CHG00

IDS ALTER NOS.

```

00238 043080 GO TO 040-RET-CUST-REC.
00239 043210 150-STORE-CUST-REC-ERR.
00240 043220 DISPLAY "STORE ERROR".
00241 043230 DISPLAY "CUSTOMER RECORD".
00242 043240 GO TO 020-READ-CARDS.
00243 043241*
00244 043242* THIS IS THE ENTRY POINT ROUTINE THAT
00245 043243* IS CALLED BY THE FORTRAN PROGRAM
00246 043244*
00247 044014 ENTER LINKAGE MODE.
00248 044015 ENTRY POINT ENTABC.
00249 044016 ENTER COBOL.
00250 044020 MOVE SPACES TO WORK-LINE.
00251 044030 WRITE PRINT-LINE FROM WORK-LINE
00252 044040 BEFORE ADVANCING TO TOP OF PAGE.
00253 044045* SET UP AND PRINT REPORT HEADINGS
00254 044050 MOVE "CUSTOMER NUMBERS AND ACCOUNTS STORED ON DATA FILE"
00255 044060 TO TITLE-1.
00256 044070 WRITE PRINT-LINE FROM WORK-LINE BEFORE ADVANCING 2 LINES.
00257 044080 MOVE SPACES TO WORK-LINE.
00258 044090 MOVE MONTH TO MONTH-P.
00259 044100 MOVE DAY TO DAY-P.
00260 044110 MOVE YEAR TO YEAR-P.
00261 044130 MOVE "-" TO DASH-1, DASH-2.
00262 044140 WRITE PRINT-LINE FROM WORK-LINE BEFORE ADVANCING 2 LINES.
00263 044150 MOVE SPACES TO WORK-LINE.
00264 044160 MOVE "CUSTOMER NUMBER" TO TITLE-10.
00265 044170 MOVE "TYPE OF ACCOUNT" TO TITLE-20.
00266 044180 MOVE "ACCOUNT NO" TO TITLE-30.
00267 044190 MOVE "AMOUNT" TO TITLE-40.
00268 044200 WRITE PRINT-LINE FROM WORK-LINE BEFORE ADVANCING 2 LINES.
00269 044210 MOVE SPACES TO WORK-LINE.
00270 044220 MOVE 000001 TO ENTRY-FIELD.
00271 044230 ENTER IDS.
00272 044240 RETRIEVE ENTRY-REC RECORD
00273 044250 IF ERROR GO TO 209-RET-ENT-ERR.
00274 044260 201-GET-CUST-CHN,
00275 044270 WRITE PRINT-LINE FROM WORK-LINE BEFORE ADVANCING 1 LINES,
00276 044275* RETRIEVE AND PRINT CUSTOMER NUMBER RECORD*
00277 044280 ENTER IDS.
00278 044290 RETRIEVE NEXT RECORD OF CUST-NO-CHN CHAIN
00279 044300 IF ERROR GO TO 210-RET-CUST-ERR ELSE
00280 044310 IF ENTRY-REC RECORD GO TO 206-CREAT-ERROR
00281 044320 ELSE MOVE.
00282 044330 MOVE CUST-NO-DSU TO CUST-NO-P.
00283 044340 203-GET-CHECK-REC,
00284 044345* RETRIEVE AND PRINT DETAIL RECORDS OF CHECK-CHN CHAIN
00285 044350 ENTER IDS.
00286 044360 RETRIEVE NEXT RECORD OF CHECK-CHN CHAIN
00287 044370 IF ERROR GO TO 211-RET-CK-ERR ELSE

```

IDS ALTER NOS.

```

00288 044380     IF CUST-NO-REC RECORD GO TO 204-GET-SAVE-REC
00289 044390     ELSE MOVE.
00290 044400     MOVE "CHECKING" TO TYPE-P.
00291 044410     MOVE ACCT-NO-CK TO ACCT-NO-P.
00292 044420     MOVE AMOUNT-CK TO AMOUNT-P.
00293 044430     WRITE PRINT-LINE FROM WORK-LINE BEFORE ADVANCING 1 LINES.
00294 044440     MOVE SPACES TO WORK-LINE.
00295 044450     GO TO 203-GET-CHECK-REC.
00296 044460 204-GET-SAVE-REC.
00297 044465*   RETRIEVE AND PRINT DETAIL RECORDS OF SAVE-CHN CHAIN
00298 044470     ENTER IDS.
00299 044480     RETRIEVE NEXT RECORD OF SAVE-CHN CHAIN
00300 044490     IF ERROR GO TO 212-RET-SA-ERR ELSE
00301 044500     IF CUST-NO-REC RECORD GO TO 205-GET-LOAN-REC
00302 044510     ELSE MOVE.
00303 044520     MOVE "SAVINGS " TO TYPE-P.
00304 044530     MOVE ACCT-NO-SA TO ACCT-NO-P.
00305 044540     MOVE AMOUNT-SA TO AMOUNT-P.
00306 044550     WRITE PRINT-LINE FROM WORK-LINE BEFORE ADVANCING 1 LINES.
00307 044560     MOVE SPACES TO WORK-LINE.
00308 044570     GO TO 204-GET-SAVE-REC.
00309 044580 205-GET-LOAN-REC.
00310 044585*   RETRIEVE AND PRINT DETAIL RECORDS OF LOAN-CHN CHAIN
00311 044590     ENTER IDS.
00312 044600     RETRIEVE NEXT RECORD OF LOAN-CHN CHAIN
00313 044610     IF ERROR GO TO 213-RET-LO-ERR ELSE
00314 044620     IF CUST-NO-REC RECORD GO TO 201-GET-CUST-CHN
00315 044630     ELSE MOVE.
00316 044640     MOVE "LOAN " TO TYPE-P.
00317 044660     MOVE ACCT-NO-LO TO ACCT-NO-P.
00318 044670     MOVE AMOUNT-LO TO AMOUNT-P.
00319 044680     WRITE PRINT-LINE FROM WORK-LINE BEFORE ADVANCING 1 LINES.
00320 044690     MOVE SPACES TO WORK-LINE.
00321 044700     GO TO 205-GET-LOAN-REC.
00322 044710 206-CREAT-ERROR.
00323 044720     WRITE PRINT-LINE FROM WORK-LINE BEFORE
00324 044730     ADVANCING TO TOP OF PAGE.
00325 044820     ENTER IDS.
00326 044830     DEBUG CURRENT BUFFER
00327 044840     RECORD
00328 044850     CCBLOC
00329 044855     TRACE CUST-NO-CHN CHAIN.
00330 044870     GO TO 300-WRAP-UP.
00331 044920 209-RET-ENT=ERR.
00332 044930     DISPLAY "RETRIEVE ERROR".
00333 044940     DISPLAY "FILE ENTRY RECORD".
00334 044950     GO TO 300-WRAP-UP.
00335 044960 210-RET-CUST-ERR.
00336 044970     DISPLAY "RETRIEVE ERROR".
00337 044980     DISPLAY "CUSTOMER RECORD".

```

IDS ALTER NOS.

```

00338 044990 GO TO 201-GET-CUST-CHN.
00339 045100 211-RET-CK-ERR.
00340 045110 DISPLAY "RETRIEVE ERROR".
00341 045120 DISPLAY "CHECK RECORD".
00342 045130 GO TO 203-GET-CHECK-REC.
00343 045140 212-RET-SA-ERR.
00344 045150 DISPLAY "RETRIEVE ERROR".
00345 045160 DISPLAY "SAVING RECORD".
00346 045170 GO TO 204-GET-SAVE-REC.
00347 045180 213-RET-LO-ERR.
00348 045190 DISPLAY "RETRIEVE ERROR".
00349 045200 DISPLAY "LOAN RECORD".
00350 045210 GO TO 205-GET-LOAN-REC.
00351 045220 300-WRAP-UP.
00352 045240 CLOSE CARD-READER, PRINT-UNIT.
00353 045245* CLOSE IDS DATA BASE
00354 045250 ENTER IDS.
00355 045260 CLOSE.
00356 045261 309-PROGRAM-EXIT.
00357 045262 EXIT ENTABC.
00358 045270 310-SNOOPY-EXIT.
00359 045280 EXIT PROGRAM.
IDS-STRUCTURE SECTION.
ENTER GMAP .
PMC ON
BLOCK ,IDS,,
RD0641 ,QRD 023,000033,0,0,0,000000.
ETC RD0641,RD0645,RD0643,0000,RD6277.
ETC 000000,000000,LOAN-REC
RD0645 ,QDD 023,10,0,0,1,1.
ETC 1,RD0641,RD0641,RD4609,RD4609,RD0645,
ETC 0029,0000,0000.
ETC LOAN-CHN
RD0643 ,QFD 0,0,000011,0006,FC4610,RD0644,
ETC RD0643,RD4610.
ETC ACCT-NO-LO
RD0644 ,QFD 3,0,000017,0012,FC6209,RD0642,
ETC RD0644,RD6209.
ETC AMOUNT-LO
RD0642 ,QFD 0,0,000005,0006,FC1153,RD0641,
ETC RD0642,RD1153.
ETC CUST-NO-LO
RD6273 ,QRD 022,000033,0,0,0,000000.
ETC RD6273,RD6277,RD6275,0000,RD1667.
ETC 000000,000000,SAVE-REC
RD6277 ,QDD 022,10,0,0,1,1.
ETC 1,RD6273,RD6273,RD5889,RD5889,RD6277,
ETC 0029,0000,0000.
ETC SAVE-CHN
RD6275 ,QFD 0,0,000011,0006,FC7745,RD6276,

```

86226 01 02-05-70 14.791 GE600 INTEGRATED STORE TRANSLATOR ISDL-2 CHG00

IDS ALTER NOS.

00001 010010 IDENTIFICATION DIVISION.
00002 010020 PROGRAM-ID, CMKSEQ.
00003 010030 AUTHOR, GEORGE A RUDOLPH.
00004 010040 DATE-WRITTEN, MAY 1969.
00005 010050 INSTALLATION, G-E - PHOENIX;
00006 010051 REMARKS, THIS IS THE CHECKING SEGMENT WHICH IS CALLED BY
00007 010052 THE MAIN PROGRAM SNOOPY TO CREATE AND STORE
00008 010053 CHECK-REC RECORDS.
00009 010060 ENVIRONMENT DIVISION.
00010 010070 CONFIGURATION SECTION.
00011 010080 SOURCE-COMPUTER, GE-635.
00012 010090 OBJECT-COMPUTER, GE-635.
00013 010091 SPECIAL-NAMES,
00014 010092 GETIME IS TODAYS-DATE.
00015 010095 BLOCK 10 IS CCBLOXX,
00016 010096 BLOCK 20 IS ENTRY-REC THRU LOAN-REC.
00017 010200 INPUT-OUTPUT SECTION.
00018 010210 FILE-CONTROL.
00019 010220 SELECT CARD-READER ASSIGN TO CR FOR CARDS.
00020 010230 SELECT IDS TEST-FILE ASSIGN TO TF.
00021 010240 I-O-CONTROL.
00022 010250 APPLY SYSTEM STANDARD FORMAT ON CARD-READER.
00023 020010 DATA DIVISION.
00024 020020 FILE SECTION.
00025 020030 FD CARD-READER
00026 020040 LABEL RECORDS ARE STANDARD
00027 020050 DATA RECORD IS CARD-IN.
00028 020060 01 CARD-IN.
00029 020070 02 ACCT-TYPE PICTURE XX.
00030 020080 88 LOAN-ACCT VALUE "LO".
00031 020090 88 SAVE-ACCT VALUE "SA".
00032 020200 88 CHECK-ACCT VALUE "CK".
00033 020210 02 CUST-NO-IN PICTURE 9(6).
00034 020220 02 ACCT-NO-IN PICTURE 9(6).
00035 020230 02 CUST-NAME-IN PICTURE X(26).
00036 020240 02 AMOUNT-IN PICTURE 9(10)V99.
00037 020250 02 FILLER PICTURE X(31).
00038 020300 WORKING-STORAGE SECTION.
00039 030010 IDS SECTION.
01 CCBLOXX ,
02 DIRECT-REFERENCE SIZE IS 8 USAGE IS COMPUTATIONAL-1
SYNCHRONIZED RIGHT.
02 FIRST-REFERENCE SIZE IS 8 USAGE IS COMPUTATIONAL-1
SYNCHRONIZED RIGHT.
02 LAST-REFERENCE SIZE IS 8 USAGE IS COMPUTATIONAL-1
SYNCHRONIZED RIGHT.
02 RECORD-TYPE SIZE IS 4 USAGE IS COMPUTATIONAL-1
SYNCHRONIZED RIGHT.
02 REC-FILE SIZE IS 6 CLASS IS ALPHANUMERIC
VALUE IS "0000TF".

86226 01 02-05-70 14,791 GE600 INTEGRATED STORE TRANSLATOR ISDL-2 CHG00

IDS ALTER NOS,

```

02 ERROR-REFERENCE SIZE IS 3 CLASS IS ALPHANUMERIC
SYNCHRONIZED RIGHT.
00040 030020 MD TEST-FILE
00041 030030 PAGE CONTAINS 1920 CHARACTERS
00042 030040 FILE CONTAINS 100 PAGES.
00043 030050 01 ENTRY-REC
00044 030060 TYPE IS 010
00045 030070 RETRIEVAL VIA CALC CHAIN
00046 030080 PAGE-RANGE IS 1 TO 1.
00047 030090 02 ENTRY-FIELD PICTURE 9(6).
00048 030200 98 CALC CHAIN DETAIL
00049 030210 RANDOMIZE ON ENTRY-FIELD.
00050 030230 98 CUST-NO-CHN CHAIN MASTER
00051 030240 CHAIN-ORDER IS SORTED.
00052 030250 01 CUST-NO-REC
00053 030260 TYPE IS 020
00054 030270 RETRIEVAL VIA CUST-NO-CHN CHAIN.
00055 030290 02 CUST-NO-DSU PICTURE 9(6).
00056 030300 02 CUST-NAME-DSU PICTURE X(20).
00057 031010 98 CUST-NO-CHN CHAIN DETAIL
00058 031020 DUPLICATES NOT ALLOWED
00059 031030 ASCENDING KEY IS CUST-NO-DSU
00060 031040 SELECT CURRENT MASTER.
00061 031050 98 CHECK-CHN CHAIN MASTER
00062 031060 CHAIN-ORDER IS FIRST.
00063 031070 98 SAVE-CHN CHAIN MASTER
00064 031080 CHAIN-ORDER IS FIRST.
00065 031090 98 LOAN-CHN CHAIN MASTER
00066 031200 CHAIN-ORDER IS FIRST.
00067 031210 01 CHECK-REC
00068 031220 TYPE IS 021
00069 031230 RETRIEVAL VIA CHECK-CHN CHAIN.
00070 031250 02 CUST-NO-CK PICTURE 9(6).
00071 031260 02 ACCT-NO-CK PICTURE 9(6).
00072 031270 02 AMOUNT-CK PICTURE S9(10)V99.
00073 031280 98 CHECK-CHN CHAIN DETAIL
00074 031290 SELECT CURRENT MASTER.
00075 032010 01 SAVE-REC
00076 032020 TYPE IS 022
00077 032030 RETRIEVAL VIA SAVE-CHN CHAIN.
00078 032050 02 CUST-NO-SA PICTURE 9(6).
00079 032060 02 ACCT-NO-SA PICTURE 9(6).
00080 032070 02 AMOUNT-SA PICTURE S9(10)V99.
00081 032080 98 SAVE-CHN CHAIN DETAIL
00082 032210 SELECT CURRENT MASTER.
00083 032220 01 LOAN-REC
00084 032230 TYPE IS 023
00085 032240 RETRIEVAL VIA LOAN-CHN CHAIN.
00086 032260 02 CUST-NO-LO PICTURE 9(6).
00087 032270 02 ACCT-NO-LO PICTURE 9(6).

```

86224 01 02-05-70 14.836 GE600 INTEGRATED STORE TRANSLATOR ISDL-2 CHG00

IDS ALTER NOS,

```
00088 032280      02 AMOUNT-LO          PICTURE S9(10)V99,
00089 032290      98 LOAN-CHN CHAIN DETAIL
00090 032320          SELECT CURRENT MASTER.
00091 040010 PROCEDURE DIVISION.
00092 042000 100-SAVE-PARA,
00093 042020      MOVE CUST-NO-IN TO CUST-NO-SA,
00094 042030      MOVE ACCT-NO-IN TO ACCT-NO-SA,
00095 042040      MOVE AMOUNT-IN TO AMOUNT-SA.
00096 042050      ENTER IDS.
00097 042060          STORE SAVE-REC RECORD
00098 042070          IF ERROR GO TO 140-STORE-SA-ERR.
00099 042080      GO TO 200-CALL-SA-END.
00100 043170 140-STORE-SA-ERR,
00101 043180      DISPLAY "STORE ERROR",
00102 043190      DISPLAY "SAVE RECORDS".
00103 043200 200-CALL-SA-END.
00104 043230      EXIT.
          IDS-STRUCTURE SECTION.
          ENTER GMAP .
          PMC      ON
          BLOCK    ,IDS.
RD0641 ,QRD      023,000033,0,0,0,000000,
          ETC      RD0641,RD0645,RD0643,0000,RD6273,
          ETC      000000,000000,LOAN-REC
RD0645 ,QDD      023,10,0,0,1,1,
          ETC      1,RD0641,RD0641,RD4609,RD4609,RD0645,
          ETC      0029,0000,0000,
          ETC      LOAN-CHN
RD0643 ,QFD      0,0,000011,0006,FC4610,RD0644,
          ETC      RD0643,RD4610,
          ETC      ACCT-NO-LO
RD0644 ,QFD      3,0,000017,0012,FC6209,RD0642,
          ETC      RD0644,RD6209,
          ETC      AMOUNT-LO
RD0642 ,QFD      0,0,000005,0006,FC1153,RD0641,
          ETC      RD0642,RD1153,
          ETC      CUST-NO-LO
RD6273 ,QRD      022,000033,0,0,0,000000,
          ETC      RD6273,RD6277,RD6275,0000,RD1664,
          ETC      000000,000000,SAVE-REC
RD6277 ,QDD      022,10,0,0,1,1,
          ETC      1,RD6273,RD6273,RD5889,RD5889,RD6277,
          ETC      0029,0000,0000,
          ETC      SAVE-CHN
RD6275 ,QFD      0,0,000011,0006,FC7745,RD6276,
          ETC      RD6275,RD7745,
          ETC      ACCT-NO-SA
RD6276 ,QFD      3,0,000017,0012,FC3137,RD6274,
          ETC      RD6276,RD3137,
          ETC      AMOUNT-SA
```

86224 01 02-05-70 14.836 GE600 INTEGRATED STORE TRANSLATOR ISDL-2 CHG00

IDS ALTER NOS,

```

00001 010010 IDENTIFICATION DIVISION,
00002 010020 PROGRAM-ID. SAVSEG.
00003 010030 AUTHOR, GEORGE A RUDOLPH,
00004 010040 DATE-WRITTEN, MAY 1969.
00005 010050 INSTALLATION, G E - PHOENIX,
00006 010051 REMARKS. THIS IS THE SAVING SEGMENT WHICH IS CALLED BY
00007 010052 THE MAIN PROGRAM SNOOPY TO CREATE AND STORE
00008 010053 SAVE-REC RECORDS.
00009 010060 ENVIRONMENT DIVISION.
00010 010070 CONFIGURATION SECTION.
00011 010080 SOURCE-COMPUTER, GE-635,
00012 010090 OBJECT-COMPUTER, GE-635,
00013 010091 SPECIAL-NAMES.
00014 010092 GETIME IS TODAY8-DATE,
00015 010095 BLOCK 10 IS CCBLOXK,
00016 010096 BLOCK 20 IS ENTRY-REC THRU LOAN-REC.
00017 010200 INPUT-OUTPUT SECTION.
00018 010210 FILE-CONTROL.
00019 010220 SELECT CARD-READER ASSIGN TO CR FOR CARDS.
00020 010230 SELECT IDS TEST-FILE ASSIGN TO TF.
00021 010240 I-O-CONTROL.
00022 010250 APPLY SYSTEM STANDARD FORMAT ON CARD-READER.
00023 020010 DATA DIVISION.
00024 020020 FILE SECTION.
00025 020030 FD CARD-READER
00026 020040 LABEL RECORDS ARE STANDARD
00027 020050 DATA RECORD IS CARD-IN.
00028 020060 01 CARD-IN.
00029 020070 02 ACCT-TYPE PICTURE XX.
00030 020080 08 LOAN-ACCT VALUE "LO".
00031 020090 08 SAVE-ACCT VALUE "SA".
00032 020200 08 CHECK-ACCT VALUE "CK".
00033 020210 02 CUST-NO-IN PICTURE 9(6).
00034 020220 02 ACCT-NO-IN PICTURE 9(6).
00035 020230 02 CUST-NAME-IN PICTURE X(25).
00036 020240 02 AMOUNT-IN PICTURE 9(10)V99.
00037 020250 02 FILLER PICTURE X(31).
00038 020300 WORKING-STORAGE SECTION,
00039 030010 IDS SECTION.
01 CCBLOXK ,
02 DIRECT-REFERENCE SIZE IS 8 USAGE IS COMPUTATIONAL-1
SYNCHRONIZED RIGHT.
02 FIRST-REFERENCE SIZE IS 8 USAGE IS COMPUTATIONAL-1
SYNCHRONIZED RIGHT.
02 LAST-REFERENCE SIZE IS 8 USAGE IS COMPUTATIONAL-1
SYNCHRONIZED RIGHT.
02 RECORD-TYPE SIZE IS 4 USAGE IS COMPUTATIONAL-1
SYNCHRONIZED RIGHT.
02 REC-FILE SIZE IS 6 CLASS IS ALPHANUMERIC
VALUE IS "0000TF".

```

86225 01 02-05-70 14.809 GE600 INTEGRATED STORE TRANSLATOR ISDL-2 CHG00

IDS ALTER NOS.

```
02 ERROR-REFERENCE SIZE IS 3 CLASS IS ALPHANUMERIC
SYNCHRONIZED RIGHT.
00040 030020 MD TEST-FILE
00041 030030 PAGE CONTAINS 1920 CHARACTERS
00042 030040 FILE CONTAINS 100 PAGES;
00043 030050 01 ENTRY-REC
00044 030060 TYPE IS 010
00045 030070 RETRIEVAL VIA CALC CHAIN
00046 030080 PAGE-RANGE IS 1 TO 1.
00047 030090 02 ENTRY-FIELD PICTURE 9(6).
00048 030200 98 CALC CHAIN DETAIL
00049 030210 RANDOMIZE ON ENTRY-FIELD.
00050 030230 98 CUST-NO-CHN CHAIN MASTER
00051 030240 CHAIN-ORDER IS SORTED.
00052 030250 01 CUST-NO-REC
00053 030260 TYPE IS 020
00054 030270 RETRIEVAL VIA CUST-NO-CHN CHAIN.
00055 030290 02 CUST-NO-DSU PICTURE 9(6).
00056 030300 02 CUST-NAME-DSU PICTURE X(20).
00057 031010 98 CUST-NO-CHN CHAIN DETAIL
00058 031020 DUPLICATES NOT ALLOWED
00059 031030 ASCENDING KEY IS CUST-NO-DSU
00060 031040 SELECT CURRENT MASTER.
00061 031050 98 CHECK-CHN CHAIN MASTER
00062 031060 CHAIN-ORDER IS FIRST.
00063 031070 98 SAVE-CHN CHAIN MASTER
00064 031080 CHAIN-ORDER IS FIRST.
00065 031090 98 LOAN-CHN CHAIN MASTER
00066 031200 CHAIN-ORDER IS FIRST.
00067 031210 01 CHECK-REC
00068 031220 TYPE IS 021
00069 031230 RETRIEVAL VIA CHECK-CHN CHAIN.
00070 031250 02 CUST-NO-CK PICTURE 9(6).
00071 031260 02 ACCT-NO-CK PICTURE 9(6).
00072 031270 02 AMOUNT-CK PICTURE S9(10)V99.
00073 031280 98 CHECK-CHN CHAIN DETAIL
00074 031290 SELECT CURRENT MASTER.
00075 032010 01 SAVE-REC
00076 032020 TYPE IS 022
00077 032030 RETRIEVAL VIA SAVE-CHN CHAIN.
00078 032050 02 CUST-NO-SA PICTURE 9(6).
00079 032060 02 ACCT-NO-SA PICTURE 9(6).
00080 032070 02 AMOUNT-SA PICTURE S9(10)V99.
00081 032080 98 SAVE-CHN CHAIN DETAIL
00082 032210 SELECT CURRENT MASTER.
00083 032220 01 LOAN-REC
00084 032230 TYPE IS 023
00085 032240 RETRIEVAL VIA LOAN-CHN CHAIN.
00086 032260 02 CUST-NO-LO PICTURE 9(6).
00087 032270 02 ACCT-NO-LO PICTURE 9(6).
```

86226 01 02-05-70 14.791 GE600 INTEGRATED STORE TRANSLATOR ISDL-2 CHG00

IDS ALTER NOS.

00088	032280	02	AMOUNT-LO	PICTURE S9(101V99.
00089	032290	98	LOAN-CHN CHAIN DETAIL	
00090	032320		SELECT CURRENT MASTER.	

86226 01 02-05-70 14.791 GE600 INTEGRATED STORE TRANSLATOR ISDL-2 CHG00

IDS ALTER NOS.

```
00091 080000*EJECT
00092 080010 PROCEDURE DIVISION.
00093 081050 100-CHECK-PARA.
00094 081070     MOVE CUST-NO-IN TO CUST-NO-CK.
00095 081080     MOVE ACCT-NO-IN TO ACCT-NO-CK.
00096 081090     MOVE AMOUNT-IN TO AMOUNT-CK.
00097 081100     ENTER IDS.
00098 081110         STORE CHECK-REC RECORD
00099 081120         IF ERROR GO TO 120-STORE-CK-ERR.
00100 081130         GO TO 200-CALL-CK-END.
00101 083090 120-STORE-CK-ERR.
00102 083100     DISPLAY "STORE ERROR".
00103 083110     DISPLAY "CHECK RECORD".
00104 083120 200-CALL-CK-END.
00105 083150     EXIT.
                IDS-STRUCTURE SECTION.
                ENTER GMAP .
                PMC      ON
                BLOCK    ,IDS.,
RD0641 ,QRD  023,000033,0,0,0,000000,
                ETC      RD0641,RD0645,RD0643,0000,RD6273,
                ETC      000000,000000,LOAN-REC
RD0645 ,QDD  023,10,0,0,1,1,
                ETC      1,RD0641,RD0641,RD4609,RD4609,RD0645,
                ETC      0029,0000,0000,
                ETC      LOAN-CHN
RD0643 ,QFD  0,0,000011,0006,FC4610,RD0644,
                ETC      RD0643,RD4610,
                ETC      ACCT-NO-LO
RD0644 ,QFD  3,0,000017,0012,FC6209,RD0642,
                ETC      RD0644,RD6209,
                ETC      AMOUNT-LO
RD0642 ,QFD  0,0,000005,0006,FC1153,RD0641,
                ETC      RD0642,RD1153,
                ETC      CUST-NO-LO
RD6273 ,QRD  022,000033,0,0,0,000000,
                ETC      RD6273,RD6277,RD6275,0000,RD1664,
                ETC      000000,000000,SAVE-REC
RD6277 ,QDD  022,10,0,0,1,1,
                ETC      1,RD6273,RD6273,RD5889,RD5889,RD6277,
                ETC      0029,0000,0000,
                ETC      SAVE-CHN
RD6275 ,QFD  0,0,000011,0006,FC7745,RD6276,
                ETC      RD6275,RD7745,
                ETC      ACCT-NO-SA
RD6276 ,QFD  3,0,000017,0012,FC3137,RD6274,
                ETC      RD6276,RD3137,
                ETC      AMOUNT-SA
RD6274 ,QFD  0,0,000005,0006,FC1025,RD6273,
                ETC      RD6274,RD1025.
```

IDS ALTER NOS.

```

00001 010010 IDENTIFICATION DIVISION.
00002 010020 PROGRAM-ID, LOASEG.
00003 010030 AUTHOR, GEORGE A RUDOLPH.
00004 010040 DATE-WRITTEN, MAY 1969.
00005 010050 INSTALLATION, G E - PHOENIX.
00006 010051 REMARKS. THIS IS THE LOAN SEGMENT WHICH IS CALLED BY
00007 010052 THE MAIN PROGRAM SNOOPY TO CREATE AND STORE
00008 010053 LOAN-REC RECORDS.
00009 010060 ENVIRONMENT DIVISION.
00010 010070 CONFIGURATION SECTION.
00011 010080 SOURCE-COMPUTER, GE-635.
00012 010090 OBJECT-COMPUTER, GE-635.
00013 010091 SPECIAL-NAMES.
00014 010092 GETIME IS TODAYS-DATE.
00015 010095 BLOEK 10 IS CCBLOXK.
00016 010096 BLOEK 20 IS ENTRY-REC THRU LOAN-REC.
00017 010200 INPUT-OUTPUT SECTION.
00018 010210 FILE-CONTROL.
00019 010220 SELECT CARD-READER ASSIGN TO CR FOR CARDS.
00020 010230 SELECT IDS TEST-FILE ASSIGN TO TF.
00021 010240 I-O-CONTROL.
00022 010250 APPLY SYSTEM STANDARD FORMAT ON CARD-READER.
00023 020010 DATA DIVISION.
00024 020020 FILE SECTION.
00025 020030 FD CARD-READER
00026 020040 LABEL RECORDS ARE STANDARD
00027 020050 DATA RECORD IS CARD-IN.
00028 020060 01 CARD-IN.
00029 020070 02 ACCT-TYPE PICTURE XX.
00030 020080 88 LOAN-ACCT VALUE "LO".
00031 020090 88 SAVE-ACCT VALUE "SA".
00032 020200 88 CHECK-ACCT VALUE "CK".
00033 020210 02 CUST-NO-IN PICTURE 9(6).
00034 020220 02 ACCT-NO-IN PICTURE 9(6).
00035 020230 02 CUST-NAME-IN PICTURE X(25).
00036 020240 02 AMOUNT-IN PICTURE 9(10)99.
00037 020250 02 FILLER PICTURE X(31).
00038 020300 WORKING-STORAGE SECTION.
00039 030010 IDS SECTION.
01 CCBLOXK .
02 DIRECT-REFERENCE SIZE IS 8 USAGE IS COMPUTATIONAL-1
SYNCHRONIZED RIGHT.
02 FIRST-REFERENCE SIZE IS 8 USAGE IS COMPUTATIONAL-1
SYNCHRONIZED RIGHT.
02 LAST-REFERENCE SIZE IS 8 USAGE IS COMPUTATIONAL-1
SYNCHRONIZED RIGHT.
02 RECORD-TYPE SIZE IS 4 USAGE IS COMPUTATIONAL-1
SYNCHRONIZED RIGHT.
02 REC-FILE SIZE IS 6 CLASS IS ALPHANUMERIC
VALUE IS "0000TF".

```

86224 01 02-05-70 14.836 GE600 INTEGRATED STORE TRANSLATOR ISDL-2 CHG00

IDS ALTER NOS,

```
02 ERROR-REFERENCE SIZE IS 3 CLASS IS ALPHANUMERIC
SYNCHRONIZED RIGHT.
00040 030020 MD TEST-FILE
00041 030030 PAGE CONTAINS 1920 CHARACTERS
00042 030040 FILE CONTAINS 100 PAGES.
00043 030050 01 ENTRY-REC
00044 030060 TYPE IS 010
00045 030070 RETRIEVAL VIA CALC CHAIN
00046 030080 PAGE-RANGE IS 1 TO 1.
00047 030090 02 ENTRY-FIELD PICTURE 9(6).
00048 030200 98 CALC CHAIN DETAIL
00049 030210 RANDOMIZE ON ENTRY-FIELD.
00050 030230 98 CUST-NO-CHN CHAIN MASTER
00051 030240 CHAIN-ORDER IS SORTED.
00052 030250 01 CUST-NO-REC
00053 030260 TYPE IS 020
00054 030270 RETRIEVAL VIA CUST-NO-CHN CHAIN.
00055 030290 02 CUST-NO-DSU PICTURE 9(6).
00056 030300 02 CUST-NAME-DSU PICTURE X(26).
00057 031010 98 CUST-NO-CHN CHAIN DETAIL
00058 031020 DUPLICATES NOT ALLOWED
00059 031030 ASCENDING KEY IS CUST-NO-DSU
00060 031040 SELECT CURRENT MASTER.
00061 031050 98 CHECK-CHN CHAIN MASTER
00062 031060 CHAIN-ORDER IS FIRST.
00063 031070 98 SAVE-CHN CHAIN MASTER
00064 031080 CHAIN-ORDER IS FIRST.
00065 031090 98 LOAN-CHN CHAIN MASTER
00066 031200 CHAIN-ORDER IS FIRST.
00067 031210 01 CHECK-REC
00068 031220 TYPE IS 021
00069 031230 RETRIEVAL VIA CHECK-CHN CHAIN.
00070 031250 02 CUST-NO-CK PICTURE 9(6).
00071 031260 02 ACCT-NO-CK PICTURE 9(6).
00072 031270 02 AMOUNT-CK PICTURE S9(10,V99).
00073 031280 98 CHECK-CHN CHAIN DETAIL
00074 031290 SELECT CURRENT MASTER.
00075 032010 01 SAVE-REC
00076 032020 TYPE IS 022
00077 032030 RETRIEVAL VIA SAVE-CHN CHAIN.
00078 032050 02 CUST-NO-SA PICTURE 9(6).
00079 032060 02 ACCT-NO-SA PICTURE 9(6).
00080 032070 02 AMOUNT-SA PICTURE S9(10,V99).
00081 032080 98 SAVE-CHN CHAIN DETAIL
00082 032210 SELECT CURRENT MASTER.
00083 032220 01 LOAN-REC
00084 032230 TYPE IS 023
00085 032240 RETRIEVAL VIA LOAN-CHN CHAIN.
00086 032260 02 CUST-NO-LO PICTURE 9(6).
00087 032270 02 ACCT-NO-LO PICTURE 9(6).
```

86225 01 02-05-70 14.809 GE600 INTEGRATED STORE TRANSLATOR ISDL-2 CHG00

IDS ALTER NOS.

```

00088 032280      02 AMOUNT-LO          PICTURE S9(10)V99.
00089 032290      98 LOAN-CHN CHAIN DETAIL
00090 032320          SELECT CURRENT MASTER.
00091 040010 PROCEDURE DIVISION.
00092 041130 100-LOAN-PARA.
00093 041150          MOVE CUST-NO-IN TO CUST-NO-LO.
00094 041160          MOVE ACCT-NO-IN TO ACCT-NO-LO.
00095 041170          MOVE AMOUNT-IN TO AMOUNT-LO.
00096 041180          ENTER IDS.
00097 041190          STORE LOAN-REC RECORD
00098 041200          IF ERROR GO TO 130-STORE-LO-ERR.
00099 041210          GO TO 200-CALL-LO-END.
00100 043130 130-STORE-LO-ERR.
00101 043140          DISPLAY "STORE ERROR".
00102 043150          DISPLAY "LOAN RECORD".
00103 043160 200-CALL-LO-END.
00104 043190          EXIT.
          IDS-STRUCTURE SECTION.
          ENTER GMAP .
          PMC ON
          BLOCK ,IDS.
RD0641 ,QRD      023,000033,0,0,0,000000,
          ETC      RD0641,RD0645,RD0643,0000,RD6273,
          ETC      000000,000000,LOAN-REC
RD0645 ,QDD      023,10,0,0,1,1,
          ETC      1,RD0641,RD0641,RD4609,RD4609,RD0645,
          ETC      0029,0000,0000,
          ETC      LOAN-CHN
RD0643 ,QFD      0,0,000011,0006,FC4610,RD0644,
          ETC      RD0643,RD4610,
          ETC      ACCT-NO-LO
RD0644 ,QFD      3,0,000017,0012,FC6209,RD0642,
          ETC      RD0644,RD6209.
          ETC      AMOUNT-LO
RD0642 ,QFD      0,0,000005,0006,FC1153,RD0641,
          ETC      RD0642,RD1153.
          ETC      CUST-NO-LO
RD6273 ,QRD      022,000033,0,0,0,000000,
          ETC      RD6273,RD6277,RD6275,0000,RD1664,
          ETC      000000,000000,SAVE-REC
RD6277 ,QDD      022,10,0,0,1,1,
          ETC      1,RD6273,RD6273,RD5889,RD5889,RD6277,
          ETC      0029,0000,0000,
          ETC      SAVE-CHN
RD6275 ,QFD      0,0,000011,0006,FC7745,RD6276,
          ETC      RD6275,RD7745.
          ETC      ACCT-NO-SA
RD6276 ,QFD      3,0,000017,0012,FC3137,RD6274,
          ETC      RD6276,RD3137,
          ETC      AMOUNT-SA

```

ORIGIN 053069 ENTRY LOCATION ENTRY LOCATION ENTRY LOCATION ENTRY LOCATION ENTRY LOCATION

SUBPROGRAMS INCLUDED IN DECK.

		\$	OPTION	FORTRAN				
		\$	USE	,QMAX/1/,QAREA/1577/,QMIN/1/				
056570	020570	056570					
	BLOCK COMMON	C20	056540	C21	056534			
054560	020570	C.LDIN	054572	SNOOPY	054573	C.SNOO	056524	ENTABC 055232
	BLOCK COMMON	.IDS..	054346	C21	056534	C10	054336	C20 056540
		CR	051614					PR 053060

SUBPROGRAMS OBTAINED FROM SYSTEM LIBRARY.

051540	110268	.SETU.	051545						
047322	102969	.FRDD.	051024	.FWRD.	050756	.FPRN.	050752	.FCNV.	047647
		.FFIL.	051061	.FRTN.	051060	.FRCD.	051024	.DBCNV	051814
047260	110268	.FEOP.	047260						
047122	073069	.FSLEW	047122	EXIT	046736	.FEXIT	046736	.FBAD.	047105
046526	110268	.FOPEN	046932	.FGTFB	046926	.FJOV.	046530	.FBFTB	047106
		.FXOP.	046721	.FXEM.	046244	.FXMC.	046032	ANYERR	046155
045244	102969	FXDVC	046127	FXALT	046143	FXDV	046440	FXOPT	046066
		.FXSW1	046034	.FXSW2	046036	.FXSW3	046040	FXCODE	046046
		.FIDU.	045122			ERRLK	046163	.FLTPR	046165
045006	110268	LINK	044700	LLINK	044676	IDLINK	044721		
044670	110268	.QDEBUG	043440	H5.138	044655	LENTRY	044671		
043440	073069	.QOPEN	041412	.QTAB1	043344	H5.122	043426		
041412	082869	.QMAX	061776	.QMIN	056722				
041322	073069	.QCHN	041322	H5.186	041405				
041254	073069	.QGET	041254	H5.112	041315				
040614	073069	.QSTOR	040614	H5.127	041236				
040472	073069	.QMOVE	040472	H5.180	040607				
037436	073069	.QTLNK	037436	.QTALY	037704	H5.129	040461		
037420	110268	.QUCCB	037420	H5.131	037433				
037364	110268	.QSDSW	037364	H5.126	037414				
036770	080769	.QMNO	036770	H5.119	037355				
036410	073069	.QASC	036410	H5.182	036763				
036234	073069	.QCALC	036234	.QCAL1	036372	H5.105	036404		
035772	073069	.QGDET	035772	H5.111	036227				
035734	110268	.QSYN	035734	H5.128	035766				
035654	110268	.QUPDC	035654	H5.134	035731				
035630	110268	.QAUTH	035630	H5.183	035651				
035362	073069	.QFWD	035362	H5.110	035623				
035160	073069	.QLNK1	035344	.QLNK5	035345	.QLSW	035353	.QDLNK	035160
034776	073069	.QUDCH	034776	H5.133	035152			H5.108	035354
034706	110268	.QRUND	034706	H5.125	034770				
034614	110268	.QIYPX	034614	H5.130	034702				
034500	073069	.QADJU	034500	.QINSW	034607	H5.101	034611		

86226 02 02-06-70 00.027

ORIGIN	053069	ENTRY LOCATION				
034262	073069	.QMRAC 034262	H5.121 034473			
034222	110268	.QPACK 034222	H5.123 034257			
034010	073069	.QUIT 034010	.QUITX 034203	.QUITY 034067	H5.132 034216	
033344	073069	.QCLOS 033344	H5.107 034004			
032172	073069	.QBIC 032172	.QFLSH 033130	.QSBEF 033222	.QSEMT 032676	H5.104 033336
031760	110268	.QINV2 031760	H5.160 032164			
031672	110268	.QLAR 031672	.QLOCK 031707	.QRLS 031733	H5.192 031755	
031572	073069	.QINV1 031572	H5.159 031666			
031266	073069	.QINV3 031266	H5.161 031564			
031210	073069	.QINV4 031210	H5.162 031262			
031036	073069	.QMAP1 031036	H5.163 031205			
030554	110268	.QRTAB 030554	.QTAB3 030762	H5.164 031032		
030344	073069	.QIOS 030367	.QWRIT 030344	.QREAD 030353	.QRDB 030362	.QWAIT 030365
		H5.165 030550				
027462	073069	.QWKA 027511	.QIRBA 027514	.QAVAL 027531	.QIREF 027511	.QINIT 027512
		.QIPOS 027513	.QFOP 027607	.QPMLV 027610	.QRELV 027611	.QERTB 027613
		OUTCB 027631	OUTFD 027620	.QIDCW 027515	.FINV 027537	.EINV 027540
		.IDSF 027472	.IJRNL 027504	.QSICT 027517	.QACT 027520	.QMBUF 027523
		.INV8F 027530	.QBWA 027516	.QLCCB 027522	.QVECT 027527	.QCBUF 027524
		.QEMTY 027525	.QDBGS 027521	.QCDSW 027526	.QCREC 027532	.QCURD 027533
		.QCURT 027534	.QDP5W 027535	.QNFN 027536	.QBARG 027541	.QICTR 027542
		.QSTST 027544	.QCAST 027550	.QGCST 027554	.QGDST 027560	.QGEST 027564
		.QCHST 027570	.QHDST 027574	.QMFST 027600	.QDLST 027604	.QECAC 027612
		H5.166 030340				
026264	110268	.QUTF 026264	.QUTF1 026264	.QUTF2 026303	.QUTF3 026400	.QVFY 026712
		.QVFY4 027121	.QVFY6 027442	.QVFYI 027451	H5.145 027453	
024712	073069	.QBOD 024712	.QCLR 024745	.QCSM 024765	.QDIR 025022	.QDIRC 025652
		.QDIRF 025116	.QMCH 026047	.QMEX 026103	.QMWD 026193	.QPBK 026177
		.QSF 025672	.QDIR9 025130	H5.154 026256		
024702	073069	.QSTA 024702	.QSTA1 024702	.QSTA2 024704	H5.137 024706	
024440	102969	.CNTRY 024530	.CMXIT 024543	.CMSER 024456	.CMET 024441	.CMRET 024475
		.CMPSH 024456	.CMPOP 024467	.CMUST 024505	.CMUET 024515	.CMUEX 024522
		.FICB 024675				
024426	102969	.CDATE 024434	.CTALY 024427	.CTMP0 024430	.CTMP1 024432	.C1020 024434
024340	110268	.CMSTK 024341	.CMSTE 024424			
023756	073069	.CGOPN 023760	.CTE0F 024247	.CIOER 024311	.CIOE1 024330	
023456	110268	.COSWR 023457				
023310	110268	.COSYS 023312				
023132	073069	.CICON 023135	.CITYP 023133	.COCBF 023266	.COSIZ 023244	.CXXXX 023136
023050	110268	.COBUF 023076	.CLINE 023071	.CIBUF 023052		
022402	110268	.CNFXA 022414	.CNFXB 022661	.CNFX1 022404		
022370	110268	.CED07 022371				
022362	110268	.CED05 022363				
022244	110268	.CERPL 022245				
022166	110268	.CESSN 022167				
022132	110268	.CEITL 022134	.CEGET 022140	.CEPVW 022163		
022012	110268	.CERSN 022013	.CETSS 022127	.CETSN 022044		
021732	110268	.CETLS 021734	.CESTL 021734	.CERTL 021735	.CEDLS 022000	.CECHR 022001
		.CEDEC 022005	.CECHA 022006	.CESSW 021776	.CNUM 021736	.CNQU1 021736
		.CEQU1 021736	.CNQU2 021737	.CEQU2 021737	.CEZST 021740	.CENOP 021741

86226 02 02-06-70 00.027

ORIGIN	053069	ENTRY LOCATION	ENTRY LOCATION	ENTRY LOCATION	ENTRY LOCATION	ENTRY LOCATION
021726	110268	.CESAV 021742	.CEOPS 021777			
021676	102969	.CMEND 021726	X1060 021720	X1091 021721	X1095 021722	.CTBEG 021712
		.CCCC 021717	.CTCQR 021713	CORECT 021713	.CTCMT 021714	XCMNT 021714
		BEGIN 021712	XDUMP 021715	.CTIOM 021716	X4000 021716	.CTEND 021677
		.CTDMP 021715	.CTFIN 021677	XTHIII 021677	.CQUIT 021677	
021604	110268	.GHRIT 021604	.GAWRI 021604	WRITE 021604		
021510	110268	.GREAD 021510	.GAREA 021510	READ 021510		
021426	110268	.GWAIT 021426	.GAWAI 021426	WAIT 021426		
021332	110268	.GSTOT 021332	SETOUT 021332			
021302	110268	.GSTIN 021302	SETIN 021302			
021026	072569	.GEPNR 021026	EPRINT 021026			
020540	110268	.GPRNT 020540	.GAPRN 020540	PRT004 020575	PRT024 020717	PRT031 020736
		PRT032 020745	PRT035 020752	PRT051 020770	PRT002 020972	PRINT 020540
020454	110268	.GIOPG 020454	IOPO21 020530	IOPO24 020533		
020404	073069	.GWTRC 020404	.GAWTR 020404	WTREC 020404		
020270	110268	.GEDIT 020270	.GE062 020363	.GE063 020364	.GE064 020365	.GE065 020367
		.GE066 020370	.GE067 020371	.GAEDI 020270	.GE068 020372	.GE069 020373
		.GE071 020374	.GE072 020375	EDATE 020376	ETIME 020377	IOEDIT 020270
017562	073069	.GGTBK 017562	GETBK 017562	.GGET 017564	GET 017564	.GAGTB 017562
		.GAGET 017564				
017554	073069	.GOPNR 017554	.GGLSR 017554	.GGETR 017554	.GPUTR 017554	
017040	073069	.GCOPY 017040	COPY 017040	.GPTBK 017043	PUTBK 017043	.GPUT 017046
		PUT 017046	.GACOP 017040	.GAP7B 017043	.GAPUT 017046	.GFR67 017531
016742	110268	.GPISZ 016742	.GAPTS 016742	PUTSZ 016742		
016202	073069	.GOPEN 016202	.GAOPE 016202	OPEN 016202		
015530	073069	.GCLSE 015530	.GACLS 015530	.GR185 015634	.GR186 015725	.GR178 015641
		CLOSE 015530				
015512	110268	.GBNRY 015512				
015412	073069	.GRLSE 015412	.GARLS 015412	RELSE 015412		
015220	110268	.GR200 015220				
015172	110268	.GBCD 015172				
015114	110268	.GR225 015114				
015042	110268	.GR250 015042				
014550	073069	.GR275 014550				
014400	110268	.GR377 014434	.GR385 014373	.GR375 014400	.GR37X 014453	.GR390 014473
014274	110268	.GR980 014274	.GR979 014372	.GR99X 014300	.GR984 014336	.GR985 014372
		.GR999 014304				
014214	110268	.GR960 014214				
013476	110268	.GINMD 013503	.GOUTH 013502	.GINTL 013501	.GOUTL 013500	.GUSHH 013477
		.GOVRL 013504	.GLREA 013562	.GRCVY 013476		
013474	110268	.GINID 013474				
013442	110268	.GR990 013442	.GR991 013463	15AUG5 013470		
		ALLOCATED CORE	000000 THRU 061777	SIZE		
		OBJECT PROGRAM		068000		
		RELOCATABLE	013440 THRU 061777	046340		

S LINK LINKAA

86226 02 02-06-70 00.027

ORIGIN	053069	ENTRY LOCATION					
--------	--------	----------------	----------------	----------------	----------------	----------------	----------------

SUBPROGRAMS INCLUDED IN DECK.

*** NON FATAL ERROR	* C.LDIN LOADED PREVIOUSLY						
013320	020570	CHKSEG 013333	C,CHKS 013427				
BLOCK COMMON	.IDS.. 054346	C10	054336	C20	086540	CR	051614

SUBPROGRAMS OBTAINED FROM SYSTEM LIBRARY.

ALLOCATED CORE	000000	RANGE	THRU 061777	SIZE	062000
OBJECT PROGRAM					
RELOCATABLE	013320	THRU	061777	044460	
*** NON FATAL ERROR	* MISSING ROUTINE	.CFICB			
*** NON FATAL ERROR	* MISSING ROUTINE	LOASEG			
*** NON FATAL ERROR	* MISSING ROUTINE	SAVSEG			

\$ LINK LINKBB,LINKAA

SUBPROGRAMS INCLUDED IN DECK.

*** NON FATAL ERROR	* C.LDIN LOADED PREVIOUSLY						
013320	020570	SAVSEG 013333	C.SAVS 013427				
BLOCK COMMON	.IDS.. 054346	C10	054336	C20	086540	CR	051614

SUBPROGRAMS OBTAINED FROM SYSTEM LIBRARY.

ALLOCATED CORE	000000	RANGE	THRU 061777	SIZE	062000
OBJECT PROGRAM					
RELOCATABLE	013320	THRU	061777	044460	
*** NON FATAL ERROR	* MISSING ROUTINE	.CFICB			
*** NON FATAL ERROR	* MISSING ROUTINE	LOASEG			

\$ LINK LINKCC,LINKBB

SUBPROGRAMS INCLUDED IN DECK.

*** NON FATAL ERROR	* C.LDIN LOADED PREVIOUSLY						
013320	020570	LOASEG 013333	C.LOAS 013426				
BLOCK COMMON	.IDS.. 054346	C10	054336	C20	086540	CR	051614

SUBPROGRAMS OBTAINED FROM SYSTEM LIBRARY.

ALLOCATED CORE	000000	RANGE	THRU 061777	SIZE	062000
----------------	--------	-------	-------------	------	--------

86226 02 02-06-70 00.027

ORIGIN 053069 ENTRY LOCATION ENTRY LOCATION ENTRY LOCATION ENTRY LOCATION ENTRY LOCATION

OBJECT PROGRAM
RELOCATABLE 013320 THRU 061777 044460
*** NON FATAL ERROR * MISSING ROUTINE .CFICB
\$ DISC H*,X2S,8R
\$ DISC TF,X1S,9R TEMPORARY MASS STORAGE FILE
\$ DATA ,0 TEMPORARY I-D-S DATA FILE FOR DIRECTIVES
\$ SYSOUT PR ASSIGN PRINTER TO OUTPUT MEDIA CONVERSION
\$ DATA CR TEMPORARY FILE FOR CARD INPUT

FCB AND BUFFER SPACE

AVAILABLE 000101 THRU 013315 013215
FILE CTRL BLKS 013166 THRU 013316 000131
MAXIMUM BUFFER SPACE REQUIRED 001200

21k. IS THE MINIMUM MEMORY NEEDED TO LOAD THIS ACTIVITY WITH ALL FILES OPEN

EXECUTION PROGRAM ENTERED AT 056570

THERE WERE 000009 WARNING FLAGS IN THE ABOVE LOAD

CUSTOMER NUMBERS AND ACCOUNTS STORED ON DATA FILE

2-6-70

CUSTOMER NUMBER	TYPE OF ACCOUNT	ACCOUNT NO	AMOUNT
000123	CHECKING	003302	.74
	SAVINGS	000022	.00
	LOAN	002301	.10
000235	CHECKING	024501	145.71
001100	SAVINGS	000501	.09
	SAVINGS	002403	.01
004444	LOAN	000302	.00
055555	CHECKING	000904	1,987,654.32
123456	LOAN	000703	10.00
666111	CHECKING	005503	5.83

COBOL Program Output

SNUMB = 86226, ACTIVITY # = 02, REPORT CODE = 52, RECORD COUNT = 00004

NUMBER OF CHECKING ACCOUNT RECORDS READ = 4
 NUMBER OF LOAN RECORDS READ = 3
 NUMBER OF SAVING ACCOUNT RECORDS READ = 3
 TOTAL NUMBER OF RECORDS READ = 10

FORTRAN Program Output

Appendix D. Primary Subroutines

Primary subroutines are those subroutines which are called directly as a result of an I-D-S verb. The primary subroutine then calls other subroutines to perform the function. The following is a list of the I-D-S verbs and the corresponding primary subroutine which is called as a result of the verb.

<u>I-D-S Verb</u>	<u>Primary Subroutines</u>
CLOSE	.QCLOS
DELETE	.QDLTE
HEAD	.QHEAD
MODIFY	.QMDFY
MOVE	.QMOVE
OPEN	.QOPEN
RETRIEVE	.QGET
RETRIEVE CURRENT	.QGETC
RETRIEVE DIRECT	.QGETD
RETRIEVE EACH	.QGETE
RETRIEVE MASTER	} .QCHN
RETRIEVE NEXT	
RETRIEVE PRIOR	
STORE	.QSTOR

Appendix E. Sample Deck Setups

COMPILE AND EXECUTE PERMFILES

The following Deck Setup will compile and execute an I-D-S program using a permanent I-D-S data file.

1	8	16
\$	IDENT	IDSOO,PERMFILE
\$	USERID	IDSF0URYQUAD\$DATABASE
\$	IDS	
	I-D-S SOURCE DECK OR COMDK	
\$	EXECUTE	
\$	PRMFL	A1,R/W,R,IDSF0URYQUAD\$DATABASE/QUAD01
\$	PRMFL	A2,R/W,R,IDSF0URYQUAD\$DATABASE/QUAD02
\$	PRMFL	A3,R/W,R,IDSF0URYQUAD\$DATABASE/QUAD03
\$	PRMFL	A4,R/W,R,IDSF0URYQUAD\$DATABASE/QUAD04
\$	ENDJOB	
***EOF		

EXECUTE USING TEMPORARY FILES

The following Deck Setup will execute an I-D-S object program using temporary files. NOTE: The QUTU activity will initialize the database.

1	8	16
\$	IDENT	IDSOO,TEMPFILE
\$	PROGRAM	QUTU
\$	LIMITS	,24k
\$	MASS	A1,X1S,11R
\$	DISC	A2,X2S,22R
\$	DRUM	A3,X3S,11R
\$	DATA	.Q
IDS	CREATE	FC/A1/,BSSZ/480/,RNG/1,120/
IDS	CREATE	FC/A2/,BSSZ/480/,RNG/121,240/,LPP/32/
IDS	CREATE	FC/A3/,BSSZ/480/,RNG/241,360/
\$	DATA	I*
IDS	INIT	FC/A1/
IDS	INIT	FC/A2/
IDS	INIT	FC/A3/
\$	OBJECT	
	I-D-S	OBJECT DECK
\$	DKEND	
\$	EXECUTE	
\$	MASS	T1,X1S,11R
\$	DISC	T2,X2S,22R
\$	DRUM	T3,X3S,11R
\$	DATA	.Q
IDS	CREATE	FC/T1/,BSSZ/480/,RNG/1,120/
IDS	CREATE	FC/T2/,BSSZ/480/,RNG/121,240/,LPP/32/
IDS	CREATE	FC/T3/,BSSZ/480/,RNG/241,360/
\$	ENDJOB	
***EOF		

COMPILE AND EXECUTE USING PERMANENT AND TEMPORARY FILES

The following Deck Setup will compile and execute an I-D-S program using permanent and temporary files. NOTE: The QUTU activity will reload the temporary file from tape.

1	8	16
\$	IDENT	IDS00,MIXEDFILES
\$	USERID	IDSF0URYQUAD\$DATABASE
\$	PROGRAM	QUTU
\$	LIMITS	,24k
\$	DISC	A1,X2S,22R
\$	TAPE	DT,X6D
\$	DATA	.Q
IDS	CREATE	FC/A1/,BSSZ/480/,RNG/121,240/,LPP/32/
\$	DATA	I*
IDS	WRITE	FC/DT/,RNG/121,240/,ONFC/A1/
\$	IDS	
\$	I-D-S SOURCE DECK OR COMDK	
\$	EXECUTE	
\$	PRMFL	T1,R/W,R,IDSF0URYQUAD\$DATABASE/QUAD01
\$	DISC	T2,X2S,22R
\$	PRMFL	T3,R/W,R,IDSF0URYQUAD\$DATABASE/QUAD03
\$	PRMFL	T4,R/W,R,IDSF0URYQUAD\$DATABASE/QUAD04
\$	DATA	.Q
IDS	CREATE	FC/T2/,BSSZ/480/,RNG/121,240/,LPP/32/
\$	ENDJOB	
***EOF		

PRINT A PERMANENT FILE

The following Deck Setup is an example of a QUTU activity which prints a permanent file.

1	8	16
\$	IDENT	IDS00,PRINT
\$	USERID	IDSF0URYQUAD\$DATABASE
\$	PROGRAM	QUTU
\$	LIMITS	,24k
\$	PRMFL	TF,R/W,R,IDSF0URYQUAD\$DATABASE/QUAD01
\$	PRMFL	TG,R/W,R,IDSF0URYQUAD\$DATABASE/QUAD02
\$	DATA	I*
IDS	PRINT	FC/TF/,RNG/1,10/,PAGES
IDS	PRINT	FC/TG/,EMPTY
\$	ENDJOB	
***EOF		

TRACE ENTRY

The following Deck Setup will compile and execute an I-D-S program using an I-D-S Permanent File and will generate a trace entry for all calls to the I-D-S primary subroutines.

1	8	16
\$	IDENT	IDS00,TRCEDATA
\$	USERID	IDSFOURYQUAD\$DATABASE
\$	IDS	
	I-D-S	SOURCE DECK OR COMDK
\$	USE	.QSTC
\$	EXECUTE	
\$	DATA	1.Q
IDS	OPTION	TRACE
\$	PRMFL	A1,R/W,R,IDSFOURYQUAD\$DATABASE/QUAD01
\$	PRMFL	A2,R/W,R,IDSFOURYQUAD\$DATABASE/QUAD02
\$	PRMFL	A3,R/W,R,IDSFOURYQUAD\$DATABASE/QUAD03
\$	PRMFL	A4,R/W,R,IDSFOURYQUAD\$DATABASE/QUAD04
\$	ENDJOB	
***EOF		

EXECUTE QUTJ

Deck Setup to execute QUTJ from the Software Library.

1	8	16
\$	IDENT	IDS00,JOURNAL
\$	PROGRAM	QUTJ
\$	LIMITS	OPTIONS
\$	TAPE	IN,X1D,,1234,,JOURNAL-TAPE
\$	DATA	I*
IDS	SYSTEM	
\$	ENDJOB	
***EOF		

EXECUTE QUTP

Deck Setup to execute QUTP from the Software Library.

1	8	16
\$	IDENT	IDS00,PICKER
\$	PROGRAM	QUTP
\$	LIMITS	OPTIONS
\$	TAPE	IN,X1D,,1234,,JOURNAL-TAPE
\$	TAPE	OT,X2S
\$	DATA	I*
IDS	SELECT	1/53607,1/53607,B
IDS	SELECT	12/88802, 13/88802,B
\$	ENDJOB	
***EOF		

EXECUTE QUTS

Deck Setup for executing QUTS from the Software Library.

1	8	16
\$	IDENT	IDS00, SORT
\$	PROGRAM	QUTS
\$	LIMITS	10,17k
\$	TAPE	IN,X2D
\$	TAPE	OT,X3S,,99999
\$	TAPE	OU,X4S,,99999
\$	NTAPE	S1,X5R,3
\$	ENDJOB	
***EOF		

EXECUTE QUTI AND QUTC

Deck Setup for executing QUTI and QUTC from the Software Library.

1	8	16
\$	IDENT	IDS00,CALC
\$	PROGRAM	QUTI
\$	MASS	A1,D1S,10R
\$	DATA	.Q
IDS	CREATE	FC/A1/,BSSZ/100/,RNG/1,100/
\$	DATA	I*
IDS	INITIAL	1,100
\$	PROGRAM	QUTC
\$	LIMITS	10,26k
\$	TAPE	A1,A1R,,,,WORK1
\$	TAPE	B1,B1R,,,,WORK2
\$	TAPE	T1,T1D,,1234,,USER-IN
\$	TAPE	C1,C1D,,,,USER-SORTED
\$	NTAPE	S1,S1R, 3
\$	MASS	D1,D1R,10R
\$	SYSOUT	P1
\$	DATA	.Q
IDS	CREATE	FC/D1/,BSSZ/100/,RNG/1,100/
\$	DATA	I*
IDS	OPTION	GENERATE/,RANDA/,RNG/1, 30000/
\$	ENDJOB	
***EOF		

EXECUTE QUTD

Deck Setup for executing QUTD from the Software Library.

1	8	16
\$	IDENT	IDS00,DUMP
\$	PROGRAM	QUTD
\$	LIMITS	OPTIONS
\$	USERID	IDSF0URYQUAD\$DBASE
\$	PRMFL	TF,R/W,R,IDSF0URYQUAD\$DBASE/QUAD01
\$	PRMFL	TG,R/W,R,IDSF0URYQUAD\$DBASE/QUAD02
\$	TAPE	OT,X2S,,,,DUMP-FILE
\$	DATA	I*
IDS	DUMP	
\$	ENDJOB	
***EOF		

EXECUTE QUTL

Deck Setup for executing QUTL from the Software Library.

1	8	16
\$	IDENT	IDS00,LOAD
\$	PROGRAM	QUTL
\$	LIMITS	OPTIONS
\$	MASS	A1,X1R,15R
\$	TAPE	IN,X2S,,,1234,,DUMP-FILE
\$	TAPE	DE,X3S,,,,DELETE-FILE
\$	DATA	.Q
IDS	CREATE	FC/A1/,BSSZ/480/,RNG/1,120/
\$	DATA	I*
IDS	OPTION	PLOAD/,RNG/1,120/,DELETE/
\$	ENDJOB	
***EOF		

COLLECTING TYPE B STATISTICS

Deck Setup for collecting type B statistics on the journal file and executing QUTR from the Software Library.

1	8	16
\$	IDENT	IDS00,STATISTICS
\$	USERID	IDSFOURYQUAD\$DATABASE
\$	USE	.QSTB
\$	OBJECT	
\$	DKEND	
\$	EXECUTE	
\$	PRMFL	A1,R/W,R,IDSFOURYQUAD\$DATABASE/QUAD01
\$	TAPE	JX,X1S,,,,I-D-S-JOURNAL
\$	PROGRAM	QUTR
\$	SYSOUT	P1
\$	TAPE	A1,X1R,,,,I-D-S-JOURNAL
\$	TAPE	B1,X2R,,99999
\$	NTAPE	S1,T,2
\$	ENDJOB	
***EOF		

Activity 1 is the execution of an IDS program which provides for collection of type B information on the user-created journal file (JX tape).

Activity 2 is the execution of QUTR.

Appendix F. Reference Code Manipulation

EXTRACT A PAGE NUMBER

Procedure Division statements similar to the following may be used to extract a page number from a reference code.

```
COMPUTE PAGE-NO = DIRECT-REFERENCE /64.
```

EXTRACT A LINE NUMBER

Procedure Division statements similar to the following may be used to extract a line number from a reference code.

- a. Assume PAGE-NO was previously extracted.

```
COMPUTE LINE-NO = DIRECT-REFERENCE - (PAGE-NO * 64).
```

- b. Assume PAGE-NO was not previously extracted.

```
COMPUTE LINE-NO = DIRECT-REFERENCE - ((DIRECT-REFERENCE/64)*64)
```

CREATE A REFERENCE CODE

Procedure Division statements similar to the following may be used to create a reference code.

- a. Assume PAGE-NO has previously been initialized with the desired page number.

- b. Assume LINE-NO has previously been initialized with the desired line number.

COMPUTE DIRECT-REFERENCE = (PAGE-NO *64) + LINE-NO.

·
·
·
77 PAGE-NO PIC 9(6) COMP-1.
77 LINE-NO PIC 9(2) COMP-1.

·
·
·
IDS SECTION
01 CCBLOXK.
02 DIRECT-REFERENCE PIC 9(8) COMP-1.
·
·
·

Index

01	level 01 and 98	31
02	level 02	31
03	Slave Begin Sync Record Type 03	138
3	TYPE 3 Slave Begin Sync (SLVBGN)	141
4	TYPE 4 Slave End Sync (SLVEND)	141
5	TYPE 5 Before Page Image (BEFORE)	141
	Type 5 Before Page Image (BEFORE)	165
6	TYPE 6 After Page Image (AFTER)	141
	Type 6 After Page Image (AFTER)	165
9	TYPE 9 Statistics	141
98	level 01 and 98	31
ACCESS		
	concurrent access	125
	READ access mode	135
	WRITE access mode	135
	RECOVERY access mode	135
ACCESSING		
	ACCESSING AN I-D-S FILE	132

ACTIVITY	
File System Activity (\$ FILSYS)	125
Activity Number	142
Page Buffer Activity Table	152
Page Buffer Activity Table	166
activity chain	166
AFTER	
AFTER	47
TYPE 6 After Page Image (AFTER)	141
AFTER page images	145
Type 6 After Page Image (AFTER)	165
ALL	
ALL	238
ALLOCATION	
Subfile Allocation	132
subfile allocation criteria	134
I-D-S Data File Allocation	134
ALLOWED	
DUPLICATES NOT ALLOWED clause	82
ALTER	
GMAP alter number	242
ANALYZER/CALC	
Randomizing Analyzer/CALC Pre-Load Sort Utility	180
AREA	
ERROR-REFERENCE communication area	52
labeled common area	259
labeled common area (.IDS...)	264
AREAS	
ASSIGNMENT OF I-D-S BUFFER AND WORK AREAS	151
ASCENDING	
ASCENDING RANGE KEY	54
ASCENDING	75
ASCENDING/DESCENDING	
Ascending/Descending	53
ASSIGNMENT	
ASSIGNMENT OF I-D-S BUFFER AND WORK AREAS	151
ATTRIBUTES	
attributes of an I-D-S data file	154
AUTHORITY	
Authority	42
AVAILABLE	
available line flag	245

BASE		
	Base Page	168
	Data Base Load/Print Utility Routine (QUTL)	199
BASIS		
	Basis For Overlaying	257
BCD		
	BCD	234
BEFORE		
	BEFORE	47
	CHAIN-ORDER IS BEFORE	49
	TYPE 5 Before Page Image (BEFORE)	141
	BEFORE page images	145
	Type 5 Before Page Image (BEFORE)	165
BEGIN		
	Slave Begin Sync Record Type 03	138
	TYPE 3 Slave Begin Sync (SLVBGN)	141
BETWEEN		
	Communication Between Subprograms	258
	How to Communicate Between Compilers	265
	pass information between COBOL and FORTRAN	267
BINARY		
	binary	234
BLOCK		
	Communication Control Block	103
	GEFRC file control block	154
	Communications Control Block (CCBLOC)	264
BUFFER		
	ASSIGNMENT OF I-D-S BUFFER AND WORK AREAS	151
	Inventory Record Buffer	152
	Page Buffer Activity Table	152
	Data Page Buffer	153
	Buffer Format	158
	Buffer Strategy for Inventory Buffers	159
	Buffer Format	161
	Data Page Buffer	163
	Buffer Strategy for Page Buffers	166
	EMPTY buffer	166
	Page Buffer Activity Table	166
BUFFERS		
	Buffer Strategy for Inventory Buffers	159
	Buffer Strategy for Page Buffers	166
CALC		
	CALC chain	70

CALCULATED	
CALCULATED RECORDS	13
calculated records	38
calculated chain	49
Calculated records	84
CALL	
CALL statement	259
CALL LLINK	262
CALL LINK	262
CALLING	
return to the calling subprogram	259
CALL'S	
CALL's to load specific subprograms	262
CARD	
\$ IDS control card	91
\$ IDS CONTROL CARD DESCRIPTION	93
\$ USERID control card	128
\$ PRMFL control card	132
\$ USE control card	267
CATALOG	
System Master Catalog	128
CCBLOC	
Communications Control Block (CCBLOC)	264
CHAIN	
Linking Detail Record of a Chain	15
Selecting Master Record of a Chain	15
Chain Ordering	16
Prime Chain	17
Chain Processing	17
Chain NEXT	17
Chain PRIOR (optional)	17
Chain MASTER (optional)	17
Chain Tables	18
Chain Definition	28
Chain Definition	43
Chain Definition Entry	44
calculated chain	49
CALC chain	70
activity chain	166
CHAINS	
I-D-S CHAINS	4
Multiple Chains	5
CHAIN-ORDER	
CHAIN-ORDER	40
Chain-Order	47
CHAIN-ORDER IS BEFORE	49

CHARACTERISTICS	
OPERATIONAL CHARACTERISTICS	125
CHECKSUM	
Checksum	141
checksum	234
checksum	236
CLASSES	
Record Classes	13
CLAUSE	
COBOL record description clause	32
PICTURE clause	32
Editing clause	32
PAGE-RANGE clause	38
INTERVAL clause	40
PAGE-RANGE clause	40
RETRIEVAL VIA clause	75
DUPLICATES NOT ALLOWED clause	82
USE clause	89
CLOSE	
Close	62
CLOSING	
Closing Journal Files	142
COBOL	
COBOL record description clause	32
COBOL procedural statements	32
OVERLAYING A COBOL PROGRAM	257
USING I-D-S WITH A COBOL OVERLAYED PROGRAM	264
FORTRAN - INTERFACING WITH COBOL AND I-D-S	265
pass information between COBOL and FORTRAN	267
CODE	
R11 error code	71
reference code	74
reference code	76
Termination Code	141
directive file code is I*	232
REFERENCE CODE MANIPULATION	303
COMDK	
PAGE EJECT AND COMDK LABELING	91
COMDK Labeling	91
COMMON	
labeled common	25
labeled common area	259
labeled common area (.IDS...)	264
COMMUNICATE	
How to Communicate Between Compilers	265

COMMUNICATION	
ERROR-REFERENCE communication area	52
Communication Control Block	103
Communication Between Subprograms	258
COMMUNICATIONS	
Communications Control Block (CCBLOC)	264
COMPILE	
Translate and Compile	97
Translate, Compile, and Execute	98
COMPILERS	
How to Communicate Between Compilers	265
COMPLETE	
Complete trace entry	242
Complete PRTREC entry	242
CONCURRENT	
concurrent access	125
CONDITIONAL	
I-D-S Conditional Statements	85
CONDITIONS	
I-D-S ERROR CONDITIONS	251
CONFIGURATION	
Configuration Section	25
I-D-S Journal File Configuration	137
CONSIDERATION	
Consideration When Mixing Software	267
CONSTANT	
Constant Section	28
CONTENTS	
Field contents	242
CONTROL	
\$ IDS control card	91
\$ IDS CONTROL CARD DESCRIPTION	93
Communication Control Block	103
Control Definition	114
.QCD - CONTROL DEFINITION	124
\$ USERID control card	128
\$ PRMFL control card	132
Record control word	142
Slave I-D-S Control Table	152
SLAVE I-D-S CONTROL TABLE	154
GEFRC file control block	154
Slave I-D-S Control Table	154
Slave I-D-S Control Table (SICT)	155

CONTROL (continued)	
Total Control Entry	155
Control field	242
transferring control during execution	259
Communications Control Block (CCBLOC)	264
\$ USE control card	267
COPY	
COPY	32
CREATING	
CREATING AN I-D-S DATA FILE	126
Creating a Permanent I-D-S Data File	126
Creating a Temporary I-D-S Data File	129
CRITERIA	
subfile allocation criteria	134
CRMAST	
CRMAST directive	128
CURRENT	
SELECT CURRENT MASTER	49
CURRENT record	76
CURRENT record	82
Current type of I-D-S operation	242
Current record type	242
Page and line number of current I-D-S record	242
DATA	
DATA ORGANIZATION	3
SUMMARY OF DATA STRUCTURES	12
DATA DIVISION	28
Data Division	74
Data Division	82
I-D-S DATA FILE STRUCTURE DESCRIPTION	101
I-D-S DATA FILE INITIALIZATION	125
CREATING AN I-D-S DATA FILE	126
Creating a Permanent I-D-S Data File	126
I-D-S Data File Structure	128
I-D-S data file name	128
Creating a Temporary I-D-S Data File	129
.Q data file	129
I-D-S data file	131
I-D-S Data File Allocation	134
RECOVERING AN I-D-S DATA FILE	145
Data Page Buffer	153
attributes of an I-D-S data file	154
I-D-S DATA PAGES	161
Data Page Buffer	163
I-D-S DATA RECORDS	173
PERMANENT I-D-S DATA FILE	177
TEMPORARY I-D-S DATA FILE	178
TEMPORARY AND PERMANENT I-D-S DATA FILE	178
Data Base Load/Print Utility Routine (QUTL)	199
Data Type	242

DATE		
Date		141
DEALLOCATION		
Subfile Deallocation		136
DEBUG		
Debug		63
DEBUG OPTIONS		237
DECK		
DECK SETUPS		97
deck setup for an I-D-S sort		152
SAMPLE DECK SETUPS		295
DEFINING		
defining ENTRY POINTS		260
DEFINITION		
Chain Definition		28
Chain Definition		43
Chain Definition Entry		44
DEFINITION STRUCTURE		101
Record Definition Entry		104
Detail Definition		107
Master Definition		110
Field Definition		112
Control Definition		114
.QRD - RECORD DEFINITION		120
.QDD - DETAIL DEFINITION		121
.QMD - MASTER DEFINITION		122
.QFD - FIELD DEFINITION		123
.QCD - CONTROL DEFINITION		124
DELAY		
IDSEJ DELAY		142
DELETE		
Delete		64
DESCENDING		
DESCENDING		75
DESCRIPTION		
File Description		28
Record Description		28
File Description		28
I-D-S File Description Entry		29
Record Description		31
COBOL record description clause		32
I-D-S Record Description Entry		33
\$ IDS CONTROL CARD DESCRIPTION		93
I-D-S DATA FILE STRUCTURE DESCRIPTION		101
Record Description		159
Page Description		167

DESCRIPTIONS	
UTILITY PROGRAM AND SUBROUTINE DESCRIPTIONS	179
DETAIL	
Linking Detail Record of a Chain	15
detail records	41
Detail Definition	107
.QDD - DETAIL DEFINITION	121
DIRECT	
RETRIEVE DIRECT	86
DIRECTIVE	
CRMAST directive	128
Directive Processor and Service Subroutine (.QDIR)	232
directive file code is I*	232
directive	232
variable field of a directive	233
directive	233
I-D-S Directive	237
DIRECTIVES	
DIRECTIVES	238
DIRECT-REFERENCE	
DIRECT-REFERENCE	75
DIRECT-REFERENCE	82
DISC	
\$ DISC	157
DIVISION	
IDENTIFICATION DIVISION	23
ENVIRONMENT DIVISION	23
DATA DIVISION	28
Procedure Division	42
PROCEDURE DIVISION	61
Data Division	74
Data Division	82
DO	
DO	238
DONTDO	
DONTDO	238
DUMP	
Journal Tape Dump Utility Program (QUTJ)	195
DUMP/PRINT	
Storage Tape Dump/Print Utility Routine (QUTD)	187
DUPLICATE	
DUPLICATE records	71

DUPLICATES	
Duplicates	52
DUPLICATES NOT ALLOWED clause	82
DURING	
transferring control during execution	259
EACH	
RETRIEVE EACH	86
EDITING	
Editing clause	32
EJECT	
PAGE EJECT AND COMDK LABELING	91
Page Eject in the Listing	91
EMPTY	
EMPTY buffer	166
END	
TYPE 4 Slave End Sync (SLVEND)	141
ENTER	
ENTER IDS	61
ENTRIES	
Individual File Entries	156
ENTRY	
I-D-S File Description Entry	29
I-D-S Record Description Entry	33
Chain Definition Entry	44
Record Definition Entry	104
Total Control Entry	155
USER ENTRY POINT	241
user entry point (QSTA4)	241
Complete trace entry	242
Complete PRTREC entry	242
I-D-S error entry	242
defining ENTRY POINTS	260
ENTRY POINT statement,	260
ENVIRONMENT	
ENVIRONMENT DIVISION	23
ERROR	
R11 error code	71
I-D-S error	241
I-D-S error entry	242
I-D-S ERROR CONDITIONS	251
ERROR-REFERENCE	
ERROR-REFERENCE communication area	52
ERROR-REFERENCE	87
ERROR-REFERENCE	251

ETC		
ETC		206
EXAMPLES		
Examples		143
EXECUTE		
Translate, Compile, and Execute		98
EXECUTION		
OBJECT PROGRAM EXECUTION		99
I-D-S EXECUTION REPORT		147
Execution Report		196
Execution Report		208
execution report		235
Execution Report		246
transferring control during execution		259
EXECUTION INFORMATION		
Execution Information Report Program (QUTR)		210
EXIT		
EXIT statement		259
FIELD		
prime retrieval field		35
sort key field		70
randomize field		70
match-key field		71
Field Definition		112
.QFD - FIELD DEFINITION		123
variable field of a directive		233
Field contents		242
Control field		242
FIELD-NAME		
Field-name of record		242
FILE		
file name		27
File Description		28
File Description		28
I-D-S File Description Entry		29
I-D-S DATA FILE STRUCTURE DESCRIPTION		101
File System Activity (\$ FILSYS)		125
I-D-S DATA FILE INITIALIZATION		125
CREATING AN I-D-S DATA FILE		126
Creating a Permanent I-D-S Data File		126
I-D-S Data File Structure		128
I-D-S data file name		128
Creating a Temporary I-D-S Data File		129
.Q data file		129
I-D-S data file		131
ACCESSING AN I-D-S FILE		132
I-D-S Data File Allocation		134

FILE (continued)	
I-D-S JOURNAL FILE	136
I-D-S Journal File Configuration	137
Journal File Map	144
RECOVERING AN I-D-S DATA FILE	145
attributes of an I-D-S data file	154
GEFRC file control block	154
Individual File Entries	156
PERMANENT I-D-S DATA FILE	177
TEMPORARY I-D-S DATA FILE	178
TEMPORARY AND PERMANENT I-D-S DATA FILE	178
File Utility Program (QUTU)	217
directive file code is I*	232
journal file	236
FILE OPTION	238
FILES	
Mixing Temporary and Permanent Files	131
Closing Journal Files	142
FILE-CONTROL	
File-Control Paragraph	27
FILE-CONTROL paragraph	29
FILE-NAME	
file-name	29
FILLER	
FILLER	32
FILSYS	
File System Activity (\$ FILSYS)	125
FIRST	
FIRST	40
FIRST	47
FIRST-REFERENCE	
FIRST-REFERENCE	76
FLAG	
line flag	244
available line flag	245
FORMAT	
Journal Record Format	137
Buffer Format	158
Buffer Format	161
Tape Format	207
Printer Format	246
FORTRAN	
FORTRAN - INTERFACING WITH COBOL AND I-D-S	265
FORTRAN subprogram	266
pass information between COBOL and FORTRAN	267

GECALL		
GECALL		91
GECHEK		
MME GECHEK and MME GEROLL		147
GEFRC		
GEFRC file control block		154
GEIDSE		
MME GEIDSE		145
GENERATED		
I-D-S GENERATED GMAP SYMBOLS		249
GEROLL		
MME GECHEK and MME GEROLL		147
GMAP		
GMAP alter number		242
I-D-S GENERATED GMAP SYMBOLS		249
GO		
Go		66
HEAD		
Head		67
HEADER		
PRTREC header		242
HEADING		
TRACE heading		242
IDENTIFICATION		
IDENTIFICATION DIVISION		23
IDS		
SELECT IDS		27
IDS Section		28
ENTER IDS		61
IDS Section		74
IDS Section		82
\$ IDS control card		91
\$ IDS CONTROL CARD DESCRIPTION		93
IDSEJ		
IDSEJ typein		142
IDSEJ DELAY		142
IDS-SPECIAL-NAMES		
IDS-Special-Names Paragraph		25
IF		
IF		86

IMAGE	
TYPE 5 Before Page Image (BEFORE)	141
TYPE 6 After Page Image (AFTER)	141
Type 5 Before Page Image (BEFORE)	165
Type 6 After Page Image (AFTER)	165
IMAGES	
BEFORE page images	145
AFTER page images	145
IMPERATIVE	
I-D-S Imperative Statements	61
INDICATOR	
level indicator MD	28
Indicator	141
INDIVIDUAL	
Individual File Entries	156
INFORMATION	
pass information between COBOL and FORTRAN	267
INITIALIZATION	
I-D-S DATA FILE INITIALIZATION	125
INITIALIZE	
Page Initialize Utility Routine (QUTI)	192
INPUT-OUTPUT	
Input-Output Section	27
INTERFACING	
FORTRAN - INTERFACING WITH COBOL AND I-D-S	265
INTERVAL	
INTERVAL	38
INTERVAL clause	40
Interval	41
INTERVAL	83
INVENTORY	
inventory records	84
Inventory Record Buffer	152
I-D-S INVENTORY RECORDS	158
Buffer Strategy for Inventory Buffers	159
I*	
directive file code is I*	232
I-D-S	
I-D-S CHAINS	4
I-D-S RECORDS	14
I-D-S PROGRAMMING LANGUAGE	23
I-D-S File Description Entry	29
I-D-S Record Description Entry	33

I-D-S (continued)	
I-D-S Imperative Statements	61
I-D-S Conditional Statements	85
I-D-S DATA FILE STRUCTURE DESCRIPTION	101
I-D-S DATA FILE INITIALIZATION	125
CREATING AN I-D-S DATA FILE	126
Creating a Permanent I-D-S Data File	126
I-D-S Data File Structure	128
I-D-S data file name	128
Creating a Temporary I-D-S Data File	129
I-D-S data file	131
ACCESSING AN I-D-S FILE	132
I-D-S Data File Allocation	134
I-D-S JOURNAL FILE	136
I-D-S Journal File Configuration	137
RECOVERING AN I-D-S DATA FILE	145
I-D-S EXECUTION REPORT	147
ASSIGNMENT OF I-D-S BUFFER AND WORK AREAS	151
deck setup for an I-D-S sort	152
Slave I-D-S Control Table	152
SLAVE I-D-S CONTROL TABLE	154
attributes of an I-D-S data file	154
Slave I-D-S Control Table	154
Slave I-D-S Control Table (SICT)	155
I-D-S INVENTORY RECORDS	158
I-D-S DATA PAGES	161
I-D-S DATA RECORDS	173
I-D-S UTILITY PROGRAMS AND SUBROUTINES	177
PERMANENT I-D-S DATA FILE	177
TEMPORARY I-D-S DATA FILE	178
TEMPORARY AND PERMANENT I-D-S DATA FILE	178
I-D-S Directive	237
I-D-S error	241
Current type of I-D-S operation	242
Page and line number of current I-D-S record	242
I-D-S error entry	242
I-D-S modify routine	242
I-D-S RESERVED WORDS	249
I-D-S GENERATED GMAP SYMBOLS	249
I-D-S ERROR CONDITIONS	251
USING I-D-S WITH A COBOL OVERLAYED PROGRAM	264
FORTRAN - INTERFACING WITH COBOL AND I-D-S	265
 I/O	
I/O request for a page	154
 JOB	
Job Number	142
 JOURNAL	
I-D-S JOURNAL FILE	136
I-D-S Journal File Configuration	137
Journal Record Format	137
Closing Journal Files	142

JOURNAL (continued)	
Journal Override	143
Journal File Map	144
Journal Tape Dump Utility Program (QUTJ)	195
Journal Record Selector Utility Program (QUTP)	206
journal file	236
KEY	
ASCENDING RANGE KEY	54
sort key field	70
sort key	75
LABELED	
labeled common	25
labeled common area	259
labeled common area (.IDS...)	264
LABELING	
PAGE EJECT AND COMDK LABELING	91
COMDK Labeling	91
LANGUAGE	
I-D-S PROGRAMMING LANGUAGE	23
LAST	
LAST	40
LAST	47
LAST-REFERENCE	
LAST-REFERENCE	76
LEVEL	
level indicator MD	28
level 01 and 98	31
level 02	31
LINE	
Page and line number of current I-D-S record	242
line flag	244
available line flag	245
LINK	
CALL LINK	262
LINKED	
LINKED TO PRIOR	49
Linked Prior	50
LINKED-MASTER	
Linked-Master	60
LINKING	
Linking Detail Record of a Chain	15
LISTING	
Page Eject in the Listing	91

LLINK		
CALL LLINK		262
LOAD		
CALL's to load specific subprograms		262
LOAD/PRINT		
Data Base Load/Print Utility Routine (QUTL)		199
MACRO		
.QNAMS macro		241
MANAGEMENT		
MEMORY MANAGEMENT		151
MANIPULATION		
REFERENCE CODE MANIPULATION		303
MAP		
Journal File Map		144
MASS		
\$ MASS		157
MASTER		
Selecting Master Record of a Chain		15
Chain MASTER (optional)		17
primary master records		41
SELECT UNIQUE MASTER		49
SELECT CURRENT MASTER		49
master record		71
range master		82
master record		83
Master Definition		110
.QMD - MASTER DEFINITION		122
System Master Catalog		128
MASTER/DETAIL		
Master/Detail		45
MATCH-KEY		
Match-Key		57
match-key field		71
MATCH-KEY		75
MD		
level indicator MD		28
MEMORY		
MEMORY MANAGEMENT		151
MESSAGES		
messages		235

MIXING		
	Mixing Temporary and Permanent Files	131
	Consideration When Mixing Software	267
MME		
	MME GEIDSE	145
	MME GECHK and MME GEROLL	147
MODE		
	READ access mode	135
	WRITE access mode	135
	RECOVERY access mode	135
MODIFY		
	MODIFY	32
	Modify	70
	I-D-S modify routine	242
MOVE		
	MOVE	32
	Move	72
MULTIPLE		
	Multiple Chains	5
NAME		
	file name	27
	I-D-S data file name	128
NEAR		
	PLACE NEAR	38
	Place Near	40
	PLACE NEAR	41
	PLACE NEAR	82
	PLACE NEAR	83
NEXT		
	Chain NEXT	17
	RETRIEVE NEXT	86
NOT		
	DUPLICATES NOT ALLOWED clause	82
NULL		
	NULL	238
NUMBER		
	Job Number	142
	Activity Number	142
	Sequence Number	142
	GMAP alter number	242
	Page and line number of current I-D-S record	242
OBJECT		
	OBJECT PROGRAM EXECUTION	99

OCCURS		
OCCURS		32
ONFC/XX/		
ONFC/xx/		238
OPEN		
OPEN statement		42
Open		73
OPERATION		
Current type of I-D-S operation		242
OPERATIONAL		
OPERATIONAL CHARACTERISTICS		125
OPTION		
FILE OPTION		238
OPTIONAL		
Chain PRIOR (optional)		17
Chain MASTER (optional)		17
OPTIONS		
DEBUG OPTIONS		237
OPTIONS		238
ORDERING		
Chain Ordering		16
ORGANIZATION		
DATA ORGANIZATION		3
OVERFLOW		
Overflow rule		84
OVERLAYED		
USING I-D-S WITH A COBOL OVERLAYED PROGRAM		264
OVERLAYING		
OVERLAYING A COBOL PROGRAM		257
Basis For Overlaying		257
Overlaying Procedure		262
OVERRIDE		
Journal Override		143
PAGE		
PAGE EJECT AND COMDK LABELING		91
Page Eject in the Listing		91
TYPE 5 Before Page Image (BEFORE)		141
TYPE 6 After Page Image (AFTER)		141
BEFORE page images		145
AFTER page images		145
Page Buffer Activity Table		152

PAGE (continued)	
Data Page Buffer	153
I/O request for a page	154
Data Page Buffer	163
Type 5 Before Page Image (BEFORE)	165
Type 6 After Page Image (AFTER)	165
Buffer Strategy for Page Buffers	166
Page Buffer Activity Table	166
Page Description	167
Base Page	168
Page Initialize Utility Routine (QUTI)	192
top of page	235
Page and line number of current I-D-S record	242
PAGES	
I-D-S DATA PAGES	161
PAGETTE	
Pagette	170
PAGE-RANGE	
Page-Range	38
PAGE-RANGE clause	38
PAGE-RANGE clause	40
page-range	41
PAGE-RANGE	83
PARAGRAPH	
IDS-Special-Names Paragraph	25
File-Control Paragraph	27
FILE-CONTROL paragraph	29
PASS	
pass information between COBOL and FORTRAN	267
PERFORM	
Perform	88
PERMANENT	
Creating a Permanent I-D-S Data File	126
Mixing Temporary and Permanent Files	131
PERMANENT I-D-S DATA FILE	177
TEMPORARY AND PERMANENT I-D-S DATA FILE	178
PICTURE	
PICTURE clause	32
PLACE	
PLACE NEAR	38
Place Near	40
PLACE NEAR	41
PLACE NEAR	82
PLACE NEAR	83
POINT	
USER ENTRY POINT	241
user entry point (QSTA4)	241
ENTRY POINT statement,	260

POINTS		
defining ENTRY POINTS		260
PRE-LOAD		
Randomizing Analyzer/CALC Pre-Load Sort Utility		180
PRIMARY		
PRIMARY RECORDS		13
primary and secondary records		40
primary records		41
primary master records		41
primary record		71
primary record		82
PRIMARY SUBROUTINES		293
PRIME		
Prime Chain		17
prime retrieval field		35
PRINT		
Verify and Print Utility Subroutine (.QUTF)		244
PRINTER		
Printer Format		246
PRIOR		
Chain PRIOR (optional)		17
LINKED TO PRIOR		49
Linked Prior		50
RETRIEVE PRIOR		86
PRMFL		
\$ PRMFL control card		132
\$ PRMFL		157
PROCEDURAL		
COBOL procedural statements		32
PROCEDURE		
Procedure Division		42
PROCEDURE DIVISION		61
Overlaying Procedure		262
PROCESSING		
Chain Processing		17
TRANSLATOR PROCESSING		91
PROCESSOR		
Directive Processor and Service Subroutine (.QDIR)		232
PROGRAM		
OBJECT PROGRAM EXECUTION		99
UTILITY PROGRAM AND SUBROUTINE DESCRIPTIONS		179
Journal Tape Dump Utility Program (QUTJ)		195
Journal Record Selector Utility Program (QUTP)		206

PROGRAM (continued)	
Execution Information Report Program (QUTR)	210
Selected Record Sort Utility Program (QUTS)	213
File Utility Program (QUTU)	217
OVERLAYING A COBOL PROGRAM	257
USING I-D-S WITH A COBOL OVERLAYED PROGRAM	264
PROGRAMMING	
I-D-S PROGRAMMING LANGUAGE	23
PROGRAMS	
I-D-S UTILITY PROGRAMS AND SUBROUTINES	177
PRTREC	
PRTREC	237
Complete PRTREC entry	242
PRTREC header	242
QSTA4	
user entry point (QSTA4)	241
QUTD	
Storage Tape Dump/Print Utility Routine (QUTD)	187
QUTI	
Page Initialize Utility Routine (QUTI)	192
QUTJ	
QUTJ	147
Journal Tape Dump Utility Program (QUTJ)	195
QUTL	
Data Base Load/Print Utility Routine (QUTL)	199
QUTP	
Journal Record Selector Utility Program (QUTP)	206
QUTP	206
QUTR	
Execution Information Report Program (QUTR)	210
QUTS	
Selected Record Sort Utility Program (QUTS)	213
QUTU	
QUTU utility routine	147
File Utility Program (QUTU)	217
R11	
R11 error code	71
RANDOMIZE	
Randomize	51
randomize field	70
RANDOMIZE	75

RANDOMIZING	
Randomizing Analyzer/CALC Pre-Load Sort Utility	180
RANGE	
ASCENDING RANGE KEY	54
range master	82
READ	
READ access mode	135
RECORD	
Record Classes	13
Linking Detail Record of a Chain	15
Selecting Master Record of a Chain	15
Record Description	28
Record Description	31
COBOL record description clause	32
I-D-S Record Description Entry	33
master record	71
primary record	71
CURRENT record	76
CURRENT record	82
primary record	82
master record	83
master record	83
Record Definition Entry	104
.QRD - RECORD DEFINITION	120
Journal Record Format	137
Slave Begin Sync Record Type 03	138
Record Type	141
Record control word	142
Inventory Record Buffer	152
Record Description	159
Journal Record Selector Utility Program (QUTP)	206
Selected Record Sort Utility Program (QUTS)	213
Current record type	242
Page and line number of current I-D-S record	242
Field-name of record	242
RECORDS	
CALCULATED RECORDS	13
SECONDARY RECORDS	13
PRIMARY RECORDS	13
I-D-S RECORDS	14
calculated records	38
primary and secondary records	40
secondary records	41
primary records	41
primary master records	41
detail records	41
DUPLICATE records	71
Secondary records	83
Calculated records	84
inventory records	84
I-D-S INVENTORY RECORDS	158
I-D-S DATA RECORDS	173

RECOVERING		
RECOVERING AN I-D-S DATA FILE		145
RECOVERY		
RECOVERY access mode		135
REDEFINES		
REDEFINES		32
REFERENCE		
reference code		74
reference code		76
REFERENCE CODE MANIPULATION		303
RENAMES		
RENAMES		32
REPORT		
I-D-S EXECUTION REPORT		147
Execution Report		196
Execution Report		208
Execution Information Report Program (QUTR)		210
execution report		235
Execution Report		246
REPRESENTATION		
STRUCTURE REPRESENTATION		8
REQUEST		
I/O request for a page		154
RESERVED		
I-D-S RESERVED WORDS		249
RETRIEVAL		
Retrieval Via		35
prime retrieval field		35
RETRIEVAL VIA		38
RETRIEVAL VIA		41
RETRIEVAL VIA clause		75
RETRIEVAL VIA		82
RETRIEVAL VIA		83
retrieval statements		86
RETRIEVE		
RETRIEVE		39
Retrieve		74
RETRIEVE		85
RETRIEVE DIRECT		86
RETRIEVE EACH		86
RETRIEVE NEXT		86
RETRIEVE PRIOR		86
RETURN		
Return		77
RETURN statement		77
return to the calling subprogram		259

RNG/1B1E...5B5E/ RNG/1B,1E,...,5B,5E/	238
ROLLBACK rollback	147
ROUTINE	
QUTU utility routine	147
Storage Tape Dump/Print Utility Routine (QUTD)	187
Page Initialize Utility Routine (QUTI)	192
Data Base Load/Print Utility Routine (QUTL)	199
I-D-S modify routine	242
RULE	
Overflow rule	84
SAMPLE	
SAMPLE DECK SETUPS	295
SECONDARY	
SECONDARY RECORDS	13
primary and secondary records	40
secondary records	41
Secondary records	83
SECTION	
Configuration Section	25
Input-Output Section	27
IDS Section	28
Working-Storage Section	28
Constant Section	28
IDS Section	74
IDS Section	82
SEGMENTATION	
Segmentation	257
SELECT	
SELECT IDS	27
SELECT UNIQUE MASTER	49
SELECT CURRENT MASTER	49
Select	56
SELECT	206
SELECTED	
Selected Record Sort Utility Program (QUTS)	213
SELECTING	
Selecting Master Record of a Chain	15
SELECTOR	
Journal Record Selector Utility Program (QUTP)	206
SEQUENCE	
Sequence Number	142

SERVICE		
Directive Processor and Service Subroutine (.QDIR)		232
SETUP		
deck setup for an I-D-S sort		152
SETUPS		
DECK SETUPS		97
SAMPLE DECK SETUPS		295
SICT		
SICT Table		154
Slave I-D-S Control Table (SICT)		155
SICT table		155
SLAVE		
Slave Begin Sync Record Type 03		138
TYPE 3 Slave Begin Sync (SLVBGN)		141
TYPE 4 Slave End Sync (SLVEND)		141
Slave I-D-S Control Table		152
SLAVE I-D-S CONTROL TABLE		154
Slave I-D-S Control Table		154
Slave I-D-S Control Table (SICT)		155
SLVBGN		
TYPE 3 Slave Begin Sync (SLVBGN)		141
SLVEND		
TYPE 4 Slave End Sync (SLVEND)		141
SOFTWARE		
Consideration When Mixing Software		267
SORT		
sort key field		70
sort key		75
Sort		79
deck setup for an I-D-S sort		152
Randomizing Analyzer/CALC Pre-Load Sort Utility		180
Selected Record Sort Utility Program (QUTS)		213
SORTED		
SORTED		40
SORTED WITHIN TYPE		40
SORTED WITHIN TYPE		47
SORTED		47
SPECIFIC		
CALL's to load specific subprograms		262
STATEMENT		
OPEN statement		42
RETURN statement		77
CALL statement		259
EXIT statement		259
ENTRY POINT statement,		260

STATEMENTS	
COBOL procedural statements	32
I-D-S Imperative Statements	61
I-D-S Conditional Statements	85
retrieval statements	86
STATISTICS	
TYPE 9 Statistics	141
STORAGE	
Storage Tape Dump/Print Utility Routine (QUTD)	187
STORE	
STORE	39
Store	82
STORE	85
STRATEGY	
Buffer Strategy for Inventory Buffers	159
Buffer Strategy for Page Buffers	166
STRUCTURE	
STRUCTURE REPRESENTATION	8
I-D-S DATA FILE STRUCTURE DESCRIPTION	101
DEFINITION STRUCTURE	101
I-D-S Data File Structure	128
STRUCTURES	
SUMMARY OF DATA STRUCTURES	12
SUBFILE	
subfile	125
Subfile Allocation	132
subfile allocation criteria	134
Subfile Deallocation	136
SUBPROGRAM	
return to the calling subprogram	259
FORTRAN subprogram	266
SUBPROGRAMS	
Communication Between Subprograms	258
CALL's to load specific subprograms	262
SUBROUTINE	
UTILITY PROGRAM AND SUBROUTINE DESCRIPTIONS	179
Subroutine .QSTB	210
Directive Processor and Service Subroutine (.QDIR)	232
.QSTC subroutine	237
Verify and Print Utility Subroutine (.QUTF)	244
SUBROUTINES	
I-D-S UTILITY PROGRAMS AND SUBROUTINES	177
PRIMARY SUBROUTINES	293
SUMMARY	
SUMMARY OF DATA STRUCTURES	12

SYMBOLS	
I-D-S GENERATED GMAP SYMBOLS	249
SYMDEF	
SYMDEF	232
SYNC	
Slave Begin Sync Record Type 03	138
TYPE 3 Slave Begin Sync (SLVBGN)	141
TYPE 4 Slave End Sync (SLVEND)	141
SYNONYM	
Synonym	59
SYSTEM	
File System Activity (\$ FILSYS)	125
System Master Catalog	128
TABLE	
Slave I-D-S Control Table	152
Page Buffer Activity Table	152
SLAVE I-D-S CONTROL TABLE	154
SICT Table	154
Slave I-D-S Control Table	154
Slave I-D-S Control Table (SICT)	155
SICT table	155
Page Buffer Activity Table	166
TABLES	
Chain Tables	18
TAPE	
Storage Tape Dump/Print Utility Routine (QUTD)	187
Journal Tape Dump Utility Program (QUTJ)	195
Tape Format	207
TEMPORARY	
Creating a Temporary I-D-S Data File	129
Mixing Temporary and Permanent Files	131
TEMPORARY I-D-S DATA FILE	178
TEMPORARY AND PERMANENT I-D-S DATA FILE	178
TERMINATION	
Termination Code	141
TIME	
Time	141
TOP	
top of page	235
TOTAL	
Total Control Entry	155

TRACE	
TRACE	237
Complete trace entry	242
TRACE heading	242
TRACE	251
TRANSFERRING	
transferring control during execution	259
TRANSLATE	
Translate and Compile	97
Translate, Compile, and Execute	98
TRANSLATOR	
TRANSLATOR PROCESSING	91
TYPE	
Type	34
SORTED WITHIN TYPE	40
SORTED WITHIN TYPE	47
Slave Begin Sync Record Type 03	138
Record Type	141
TYPE 3 Slave Begin Sync (SLVBGN)	141
TYPE 4 Slave End Sync (SLVEND)	141
TYPE 5 Before Page Image (BEFORE)	141
TYPE 6 After Page Image (AFTER)	141
TYPE 9 Statistics	141
Type 5 Before Page Image (BEFORE)	165
Type 6 After Page Image (AFTER)	165
Current type of I-D-S operation	242
Current record type	242
Data Type	242
TYPEIN	
IDSEJ typein	142
TYPES/NNN...NNN/	
TYPES/nnn,...,nnn/	238
UNIQUE	
SELECT UNIQUE MASTER	49
USE	
Use	89
USE clause	89
\$ USE control card	267
USER	
USER ENTRY POINT	241
user entry point (QSTA4)	241
USERID	
\$ USERID control card	128
USING	
USING I-D-S WITH A COBOL OVERLAYED PROGRAM	264

UTILITY	
QUTU utility routine	147
I-D-S UTILITY PROGRAMS AND SUBROUTINES	177
UTILITY PROGRAM AND SUBROUTINE DESCRIPTIONS	179
Randomizing Analyzer/CALC Pre-Load Sort Utility	180
Storage Tape Dump/Print Utility Routine (QUTD)	187
Page Initialize Utility Routine (QUTI)	192
Journal Tape Dump Utility Program (QUTJ)	195
Data Base Load/Print Utility Routine (QUTL)	199
Journal Record Selector Utility Program (QUTP)	206
Selected Record Sort Utility Program (QUTS)	213
File Utility Program (QUTU)	217
Verify and Print Utility Subroutine (.QUTF)	244
VARIABLE	
variable field of a directive	233
VERBS/XXX...XXX/	
VERBS/xxx,....,xxx/	238
VERIFY	
Verify and Print Utility Subroutine (.QUTF)	244
verify	244
VIA	
Retrieval Via	35
RETRIEVAL VIA	38
RETRIEVAL VIA	41
RETRIEVAL VIA clause	75
RETRIEVAL VIA	82
RETRIEVAL VIA	83
WHEN	
Consideration When Mixing Software	267
WITH	
USING I-D-S WITH A COBOL OVERLAYED PROGRAM	264
FORTRAN - INTERFACING WITH COBOL AND I-D-S	265
WITHIN	
SORTED WITHIN TYPE	40
SORTED WITHIN TYPE	47
WORD	
Record control word	142
WORDS	
I-D-S RESERVED WORDS	249
WORK	
ASSIGNMENT OF I-D-S BUFFER AND WORK AREAS	151
WORKING-STORAGE	
Working-Storage Section	28

WRITE		
WRITE access mode		135
\$		
\$ IDS control card		91
\$ IDS CONTROL CARD DESCRIPTION		93
File System Activity (\$ FILSYS)		125
\$ USERID control card		128
\$ PRMFL control card		132
\$ PRMFL		157
\$ DISC		157
\$ MASS		157
\$ USE control card		267
.IDS...		
labeled common area (.IDS...)		264
.Q		
.Q data file		129
.QBCD		
.QBCD		234
.QCD		
.QCD - CONTROL DEFINITION		124
.QCLR		
.QCLR		234
.QCSM		
.QCSM		234
.QDD		
.QDD - DETAIL DEFINITION		121
.QDIR		
Directive Processor and Service Subroutine (.QDIR)		232
.QDIRC		
.QDIRC		233
.QFD		
.QFD - FIELD DEFINITION		123
.QMCH		
.QMCH		235
.QMD		
.QMD - MASTER DEFINITION		122
.QMEX		
.QMEX		235
.QMWD		
.QMWD		236

.QNAMS		
.QNAMS macro		241
.QPBK		
.QPBK		236
.QRD		
.QRD - RECORD DEFINITION		120
.QSFD		
.QSFD		233
.QSTB		
Subroutine .QSTB		210
.QSTC		
.QSTC subroutine		237
.QUTF		
Verify and Print Utility Subroutine (.QUTF)		244
.QUTF		246
.QUTF1		
.QUTF1		244
.QUTF2		
.QUTF2		245
.QUTF3		
.QUTF3		246
.QVFY		
.QVFY		244

HONEYWELL INFORMATION SYSTEMS
Technical Publications Remarks Form*

TITLE:

SERIES 600/6000 INTEGRATED DATA
STORE REFERENCE MANUAL

ORDER NO:

BR69, REV. 0

DATED:

JANUARY, 1971

ERRORS IN PUBLICATION:

[Empty box for reporting errors in publication]

SUGGESTIONS FOR IMPROVEMENT TO PUBLICATION:

[Empty box for providing suggestions for improvement to publication]

(Please Print)

FROM: NAME _____

DATE _____

COMPANY _____

TITLE _____

ADDRESS _____

*Your comments will be promptly investigated by appropriate technical personnel, action will be taken as required, and you will receive a written reply. If you do not require a written reply, please check here.

POSTAGE STAMP NOT
NECESSARY IF MAILED
IN THE UNITED STATES

BUSINESS REPLY MAIL: FIRST CLASS PERMIT NO. 39531, NEWTON HIGHLANDS, MASS

POSTAGE WILL BE PAID BY:

HONEYWELL INFORMATION SYSTEMS

**60 WALNUT STREET
WELLESLEY HILLS, MASS. 02181**

ATTN: U.S. GROUP PUBLICATIONS, MS 050

Honeywell

The Other Computer Company:
Honeywell

HONEYWELL INFORMATION SYSTEMS