INSTAL

```
IIIIII    NN      NN    SSSSSSSS    CCCCCCCC   MM      MM   DDDDDDD
IIIIII    NN      NN    SSSSSSSS    CCCCCCC    MM      MM   DDDDDDD
  II      NN      NN    SS          CC         MMMM  MMMM   DD      DD
  II      NN      NN    SS          CC         MMMM  MMMM   DD      DD
  II      NNNN    NN    SS          CC         MM  MM  MM   DD      DD
  II      NNNN    NN    SS          CC         MM  MM  MM   DD      DD
  II      NN  NN  NN    SSSSSS      CC               MM     DD      DD
  II      NN  NN  NN    SSSSSS      CC         MM    MM     DD      DD
  II      NN    NNNN         SS     CC         MM    MM     DD      DD
  II      NN    NNNN         SS     CC         MM    MM     DD      DD
  II      NN      NN         SS     CC         MM    MM     DD      DD
  II      NN      NN         SS     CC         MM    MM     DD      DD
IIIIII    NN      NN    SSSSSSSS    CCCCCCCC   MM    MM     DDDDDDD      ....
IIIIII    NN      NN    SSSSSSSS    CCCCCCCC   MM    MM     DDDDDDD      ....

CCCCCCCC  LL            DDDDDDD
CCCCCCCC  LL            DDDDDDD
CC        LL            DD      DD
CC        LL            DD      DD
CC        LL            DD      DD
CC        LL            DD      DD
CC        LL            DD      DD
CC        LL            DD      DD
CC        LL            DD      DD
CC        LL            DD      DD
CC        LL            DD      DD
CCCCCCCC  LLLLLLLLLL    DDDDDDD
CCCCCCCC  LLLLLLLLLL    DDDDDDD
```

```
MODULE INSCMD

  Version:      'V04-000'

!********************************************************************
!*                                                                  *
!*  COPYRIGHT (c) 1978, 1980, 1982, 1984 BY                         *
!*  DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.          *
!*  ALL RIGHTS RESERVED.                                           *
!*                                                                  *
!*  THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED  *
!*  ONLY IN  ACCORDANCE WITH  THE  TERMS  OF  SUCH  LICENSE  AND WITH THE  *
!*  INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR  ANY  OTHER  *
!*  COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY  *
!*  OTHER PERSON. NO TITLE TO AND OWNERSHIP OF  THE  SOFTWARE IS  HEREBY   *
!*  TRANSFERRED.                                                    *
!*                                                                  *
!*  THE INFORMATION IN THIS SOFTWARE IS  SUBJECT TO CHANGE WITHOUT NOTICE  *
!*  AND  SHOULD  NOT  BE  CONSTRUED AS  A COMMITMENT BY DIGITAL EQUIPMENT  *
!*  CORPORATION.                                                    *
!*                                                                  *
!*  DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE  OR  RELIABILITY OF ITS  *
!*  SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.         *
!*                                                                  *
!*                                                                  *
!********************************************************************

  MODIFIED BY:

        V03-002 MSH0061         Michael S. Harvey        5-Jul-1984
                Add EXECUTE_ONLY qualifier to ADD, CREATE and REPLACE.

        V03-001 BLS0256         Benn Schreiber           3-JAN-1984
                Make DELETE synonomous with REMOVE.

define verb ADD                            ! Synonym for CREATE
        routine INS$CREATE_VERB
        parameter p1, label=FILE_SPEC, value(required,type=$INFILE),
                prompt="Known File Entry to Install"
        qualifier LOG
        qualifier OPEN
        qualifier SHARED
        qualifier HEADER_RESIDENT
        qualifier PRIVILEGED, value (list)
        qualifier PROTECTED
        qualifier WRITEABLE
        qualifier ACCOUNTING
        qualifier PROCESS
        qualifier PURGE
        qualifier EXECUTE_ONLY
        disallow PROCESS and PRIVILEGED

define verb CREATE
        routine INS$CREATE_VERB
        parameter p1, label=FILE_SPEC, value(required,type=$INFILE),
                prompt="Known File Entry to Install"
```

```
        qualifier LOG
        qualifier OPEN
        qualifier SHARED
        qualifier HEADER_RESIDENT
        qualifier PRIVILEGED, value (list)
        qualifier PROTECTED
        qualifier WRITEABLE
        qualifier ACCOUNTING
        qualifier PROCESS
        qualifier PURGE
        qualifier EXECUTE_ONLY
        disallow PROCESS and PRIVILEGED

define verb DELETE
        routine INS$REMOVE_VERB
        parameter p1, label=FILE_SPEC, value(required,type=$INFILE),
                prompt="Known File Entry to Delete"
        qualifier PROCESS

define verb EXIT
        routine INS$EXIT_VERB

define verb HELP
        routine INS$HELP_VERB
                parameter p1, label=HELP_LINE, value(type=$REST_OF_LINE)

define verb LIST
        routine INS$LIST_VERB
        parameter p1, label=FILE_SPEC, value(type=$outfile)
        qualifier FULL
        qualifier STRUCTURE
        qualifier GLOBAL
        qualifier PROCESS

define verb PURGE
        routine INS$PURGE_VERB
        qualifier PROCESS

define verb REMOVE
        routine INS$REMOVE_VERB
        parameter p1, label=FILE_SPEC, value(required,type=$INFILE)
                prompt="Known File Entry to Remove"
        qualifier PROCESS

define verb REPLACE
        routine INS$REPLACE_VERB
        parameter p1, label=FILE_SPEC, value(required,type=$INFILE),
                prompt="Known File Entry to Replace"
        qualifier LOG
        qualifier OPEN
        qualifier SHARED
        qualifier HEADER_RESIDENT
        qualifier PRIVILEGED, value (list)
        qualifier PROTECTED
        qualifier WRITEABLE
        qualifier ACCOUNTING
```

K.11

```
    qualifier PURGE
    qualifier PROCESS
    qualifier EXECUTE_ONLY
    disallow PROCESS and PRIVILEGED
```