



\*\*FILE\*\*ID\*\*EXCREQ

B 10

|          |    |        |    |            |
|----------|----|--------|----|------------|
| RRRRRRRR |    | 333333 |    | 222222     |
| RRRRRRRR |    | 333333 |    | 222222     |
| RR       | RR | 33     | 33 | 22         |
| RR       | RR | 33     | 33 | 22         |
| RR       | RR |        | 33 | 22         |
| RR       | RR |        | 33 | 22         |
| RRRRRRRR |    |        | 33 | 22         |
| RRRRRRRR |    |        | 33 | 22         |
| RR       | RR |        | 33 | 22         |
| RR       | RR |        | 33 | 22         |
| RR       | RR | 33     | 33 | 22         |
| RR       | RR | 33     | 33 | 22         |
| RR       | RR | 333333 |    | 2222222222 |
| RR       | RR | 333333 |    | 2222222222 |

MODULE exch\$require (IDENT = 'V04-000') = %TITLE 'Facility-wide require module'

\*\*\*\*\*  
\* COPYRIGHT (c) 1978, 1980, 1982, 1984 BY  
\* DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.  
\* ALL RIGHTS RESERVED.

\* THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED  
\* ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE  
\* INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER  
\* COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY  
\* OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY  
\* TRANSFERRED.

\* THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE  
\* AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT  
\* CORPORATION.

\* DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS  
\* SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.

\*\*\*\*\*

++  
FACILITY: EXCHANGE - Foreign volume interchange facility

ABSTRACT:

This module establishes a common environment for all EXCHANGE  
modules. It contains those things that cannot be placed into  
the standard library module (EXCLIB) because of BLISS32 constraints.

ENVIRONMENT: VAX/VMS User mode

AUTHOR: CW Hobbs , CREATION DATE: 1-July-1982

MODIFIED BY:

--

## Module table of contents:

Reference the standard system library  
Reference the EXCHANGE library

## ! INCLUDE FILES:

```
LIBRARY
'SYS$LIBRARY:LIB'
;
```

```
LIBRARY
'LIBS:EXCLIB'
;
```

! Define the psects to the module-specific names. This lets us keep the plit and code for each module adjacent, which allows all non-external references to be shorter. All storage is read-only except where explicitly set to read/write.

## PSECT

```
CODE    = %NAME ($module_name_string,'_CODE')   (NOWRITE,EXECUTE),
GLOBAL  = %NAME ($module_name_string,'_PLIT')   (NOWRITE,EXECUTE),
OWN     = %NAME ($module_name_string,'_PLIT')   (NOWRITE,EXECUTE),
PLIT    = %NAME ($module_name_string,'_PLIT')   (NOWRITE,EXECUTE)
;
```

## ! Define debugging switches

## COMPILETIME

```
switch_default = 2.
```

| Default for when executed with /NOVARIANT. Normal use of the values:

- 0 - no checking, used to measure cost of checking
- 1 - production checking
- 2 - "field test" checking
- 3 - normal development mode, frequent checks, silent
- 4 - "trace" mode, most checks, print state occasionally
- 5 - "debug" mode, all checks, display all state messages

```
switch_variant = (%IF %VARIANT NEQ 0
                  %THEN %VARIANT
                  %ELSE switch_default %FI)
```

| Get the value from the command line, if it is non-zero use it, otherwise use the default

```
%IF switch_variant EQ -1
```

| Since we can't tell /VARIANT=0 from /NOVARIANT, use /VARIANT=-1 to disable checking

```
%THEN
      switch_variant = 0,
%FJ
```

```
switch_check = (switch_variant GEQ 2),
```

| performs run-time consistency checks, no message unless error

```
switch_trace = (switch_variant GEQ 4),
```

| print messages at major events and locations

```
switch_debug = (switch_variant GEQ 5)
```

| print messages at minor events and locations

```
;
```

| End of Require module SRC\$:EXCREQ

```
: END
: ELUDOM
```

0159 AH-BT13A-SE  
VAX/VMS V4.0

DIGITAL EQUIPMENT CORPORATION  
CONFIDENTIAL AND PROPRIETARY

